

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'TAILQ\_FIRST.3'

## \$ man TAILQ\_FIRST.3

TAILQ(3)

Linux Programmer's Manual

TAILQ(3)

NAME

TAILQ\_CONCAT, TAILQ\_EMPTY, TAILQ\_ENTRY, TAILQ\_FIRST, TAILQ\_FOREACH, TAILQ\_FOREACH\_REVERSE, TAILQ\_HEAD, TAILQ\_HEAD\_INITIALIZER, TAILQ\_INIT, TAILQ\_INSERT\_AFTER, TAILQ\_INSERT\_BEFORE, TAILQ\_INSERT\_HEAD, TAILQ\_INSERT\_TAIL, TAILQ\_LAST, TAILQ\_NEXT, TAILQ\_PREV, TAILQ\_REMOVE - implementation of a doubly linked tail queue

## **SYNOPSIS**

#include <sys/queue.h>

void TAILQ\_CONCAT(TAILQ\_HEAD \*head1, TAILQ\_HEAD \*head2,

TAILQ\_ENTRY NAME);

int TAILQ\_EMPTY(TAILQ\_HEAD \*head);

TAILQ\_ENTRY(TYPE);

struct TYPE \*TAILQ\_FIRST(TAILQ\_HEAD \*head);

TAILQ\_FOREACH(struct TYPE \*var, TAILQ\_HEAD \*head, TAILQ\_ENTRY NAME);

TAILQ\_FOREACH\_REVERSE(struct TYPE \*var, TAILQ\_HEAD \*head, HEADNAME,

TAILQ ENTRY NAME);

TAILQ HEAD(HEADNAME, TYPE);

TAILQ\_HEAD TAILQ\_HEAD\_INITIALIZER(TAILQ\_HEAD head);

void TAILQ\_INIT(TAILQ\_HEAD \*head);

void TAILQ\_INSERT\_AFTER(TAILQ\_HEAD \*head, struct TYPE \*listelm,

struct TYPE \*elm, TAILQ\_ENTRY NAME);

void TAILQ\_INSERT\_BEFORE(struct TYPE \*listelm, struct TYPE \*elm,

TAILQ\_ENTRY NAME);

## **DESCRIPTION**

These macros define and operate on doubly linked tail queues.

In the macro definitions, TYPE is the name of a user defined structure, that must contain a field of type TAILQ\_ENTRY, named NAME. The argument HEADNAME is the name of a user de? fined structure that must be declared using the macro TAILQ\_HEAD().

A tail queue is headed by a structure defined by the TAILQ\_HEAD() macro. This structure contains a pair of pointers, one to the first element in the tail queue and the other to the last element in the tail queue. The elements are doubly linked so that an arbitrary element can be removed without traversing the tail queue. New elements can be added to the tail queue after an existing element, before an existing element, at the head of the tail queue, or at the end of the tail queue. A TAILQ\_HEAD structure is declared as fol? lows:

TAILQ\_HEAD(HEADNAME, TYPE) head;

where struct HEADNAME is the structure to be defined, and struct TYPE is the type of the elements to be linked into the tail queue. A pointer to the head of the tail queue can later be declared as:

struct HEADNAME \*headp;

(The names head and headp are user selectable.)

The macro TAILQ HEAD INITIALIZER() evaluates to an initializer for the tail gueue head.

The macro TAILQ\_CONCAT() concatenates the tail queue headed by head2 onto the end of the one headed by head1 removing all entries from the former.

The macro TAILQ EMPTY() evaluates to true if there are no items on the tail queue.

The macro TAILQ\_ENTRY() declares a structure that connects the elements in the tail queue.

The macro TAILQ\_FIRST() returns the first item on the tail queue or NULL if the tail queue

is empty. Page 2/5

The macro TAILQ\_FOREACH() traverses the tail queue referenced by head in the forward di? rection, assigning each element in turn to var. var is set to NULL if the loop completes normally, or if there were no elements.

The macro TAILQ\_FOREACH\_REVERSE() traverses the tail queue referenced by head in the re? verse direction, assigning each element in turn to var.

The macro TAILQ\_INIT() initializes the tail queue referenced by head.

The macro TAILQ\_INSERT\_HEAD() inserts the new element elm at the head of the tail queue.

The macro TAILQ\_INSERT\_TAIL() inserts the new element elm at the end of the tail queue.

The macro TAILQ\_INSERT\_AFTER() inserts the new element elm after the element listelm.

The macro TAILQ\_INSERT\_BEFORE() inserts the new element elm before the element listelm.

The macro TAILQ\_LAST() returns the last item on the tail queue. If the tail queue is empty the return value is NULL.

The macro TAILQ\_NEXT() returns the next item on the tail queue, or NULL if this item is the last.

The macro TAILQ\_PREV() returns the previous item on the tail queue, or NULL if this item is the first.

The macro TAILQ\_REMOVE() removes the element elm from the tail queue.

#### **RETURN VALUE**

TAILQ\_EMPTY() returns nonzero if the queue is empty, and zero if the queue contains at least one entry.

TAILQ\_FIRST(), TAILQ\_LAST(), TAILQ\_NEXT(), and TAILQ\_PREV() return a pointer to the first, last, next or previous TYPE structure, respectively.

TAILQ HEAD INITIALIZER() returns an initializer that can be assigned to the queue head.

## **CONFORMING TO**

Not in POSIX.1, POSIX.1-2001 or POSIX.1-2008. Present on the BSDs. (TAILQ functions first appeared in 4.4BSD).

#### **BUGS**

The macros TAILQ\_FOREACH() and TAILQ\_FOREACH\_REVERSE() don't allow var to be removed or freed within the loop, as it would interfere with the traversal. The macros TAILQ\_FORE?

ACH\_SAFE() and TAILQ\_FOREACH\_REVERSE\_SAFE(), which are present on the BSDs but are not present in glibc, fix this limitation by allowing var to safely be removed from the list and freed from within the loop without interfering with the traversal.

EXAMPLES Page 3/5

```
#include <stddef.h>
#include <stdio.h>
#include <stdlib.h>
#include <sys/queue.h>
struct entry {
  int data;
  TAILQ_ENTRY(entry) entries;
                                       /* Tail queue. */
};
TAILQ_HEAD(tailhead, entry);
int
main(void)
{
  struct entry *n1, *n2, *n3, *np;
  struct tailhead head;
                                  /* Tail queue head. */
  int i;
  TAILQ_INIT(&head);
                                    /* Initialize the queue. */
  n1 = malloc(sizeof(struct entry));
                                      /* Insert at the head. */
  TAILQ_INSERT_HEAD(&head, n1, entries);
  n1 = malloc(sizeof(struct entry));
                                    /* Insert at the tail. */
  TAILQ_INSERT_TAIL(&head, n1, entries);
                                     /* Insert after. */
  n2 = malloc(sizeof(struct entry));
  TAILQ_INSERT_AFTER(&head, n1, n2, entries);
  n3 = malloc(sizeof(struct entry));
                                    /* Insert before. */
  TAILQ_INSERT_BEFORE(n2, n3, entries);
  TAILQ_REMOVE(&head, n2, entries);
                                            /* Deletion. */
  free(n2);
                           /* Forward traversal. */
  i = 0;
  TAILQ_FOREACH(np, &head, entries)
     np->data = i++;
                           /* Reverse traversal. */
  TAILQ_FOREACH_REVERSE(np, &head, tailhead, entries)
```

printf("%i\n", np->data);

```
n1 = TAILQ_FIRST(&head);
while (n1 != NULL) {
    n2 = TAILQ_NEXT(n1, entries);
    free(n1);
    n1 = n2;
}
TAILQ_INIT(&head);
exit(EXIT_SUCCESS);
```

/\* TailQ Deletion. \*/

## SEE ALSO

}

insque(3), queue(7)

# COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

GNU 2020-12-21 TAILQ(3)