



**Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!**

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'amixer.1'***

**\$ man amixer.1**

AMIXER(1)                      General Commands Manual                      AMIXER(1)

#### NAME

amixer - command-line mixer for ALSA soundcard driver

#### SYNOPSIS

amixer [-option] [cmd]

#### DESCRIPTION

amixer allows command-line control of the mixer for the ALSA soundcard driver. amixer supports multiple soundcards.

amixer with no arguments will display the current mixer settings for the default soundcard and device. This is a good way to see a list of the simple mixer controls you can use.

#### COMMANDS

help Shows syntax.

info Shows the information about a mixer device.

scontrols

Shows a complete list of simple mixer controls.

scontents

Shows a complete list of simple mixer controls with their contents.

set or sset <SCONTROL> <PARAMETER> ...

Sets the simple mixer control contents. The parameter can be the volume either as a percentage from 0% to 100% with % suffix, a dB gain with dB suffix (like -12.5dB), or an exact hardware value. The dB gain can be used only for the mixer elements with available dB information. When plus(+) or minus(-) letter is appended after volume value, the volume is incremented or decremented from the current value, re?

spectively.

The parameters `cap`, `nocap`, `mute`, `unmute`, `toggle` are used to change capture (recording) and muting for the group specified.

The optional modifiers can be put as extra parameters before the value to specify the stream direction or channels to apply. The modifiers `playback` and `capture` specify the stream, and the modifiers `front`, `frontleft`, `frontright`, `frontcenter`, `center`, `rear`, `rearright`, `rearleft`, `woofer` are used to specify channels to be changed.

A simple mixer control must be specified. Only one device can be controlled at a time.

`get` or `sget` <SCONTROL>

Shows the simple mixer control contents.

A simple mixer control must be specified. Only one device can be controlled at a time.

`controls`

Shows a complete list of card controls.

`contents`

Shows a complete list of card controls with their contents.

`cset` <CONTROL> <PARAMETER> ...

Sets the card control contents. The identifier has these components: `iface`, `name`, `index`, `device`, `subdevice`, `numid`. The next argument specifies the value of control.

`cget` <CONTROL>

Shows the card control contents. The identifier has same syntax as for the `cset` command.

## ADVANCED COMMANDS

`sevents`

Shows the events for the simple mixer controls.

`events` Shows the events for the mixer controls.

## OPTIONS

`-c` card

Select the card number to control. The device name created from this parameter has syntax `'hw:N'` where N is specified card number.

`-D` device

Select the device name to control. The default control name is 'default'.

-s | --stdin

Read from stdin and execute the command on each line sequentially. When this option is given, the command in command-line arguments is ignored.

Only sset and cset are accepted. Other commands are ignored. The commands to unmute matched ids are ignored without errors too.

-h Help: show syntax.

-q Quiet mode. Do not show results of changes.

-R Use the raw value for evaluating the percentage representation. This is the default mode.

-M Use the mapped volume for evaluating the percentage representation like alsamixer, to be more natural for human ear.

## EXAMPLES

```
amixer -c 1 sset Line,0 80%,40% unmute cap
```

will set the second soundcard's left line input volume to 80% and right line input to 40%, unmute it, and select it as a source for capture (recording).

```
amixer -c 1 -- sset Master playback -20dB
```

will set the master volume of the second card to -20dB. If the master has multiple channels, all channels are set to the same value.

```
amixer -c 1 set PCM 2dB+
```

will increase the PCM volume of the second card with 2dB. When both playback and capture volumes exist, this is applied to both volumes.

```
amixer -c 2 cset iface=MIXER,name='Line Playback Volume',index=1 40%
```

will set the third soundcard's second line playback volume(s) to 40%

```
amixer -c 2 cset numid=34 40%
```

will set the 34th soundcard element to 40%

## SEE ALSO

alsamixer(1)

## BUGS

None known.

## AUTHOR

amixer is by Jaroslav Kysela <perex@perex.cz>. This document is by Paul Winkler <zarmzarm@erols.com> and Jaroslav Kysela <perex@perex.cz>.

11 Aug 2000

AMIXER(1)