



**Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!**

***Rocky Enterprise Linux 9.2 Manual Pages on command 'lvm-fullreport.8'***

\$ man lvm-fullreport.8

LVM(FULLREPORT)

Red Hat, Inc.

LVM(FULLREPORT)

**NAME**

lvm fullreport - Display full report

**SYNOPSIS**

lvm fullreport

[ option\_args ]

[ position\_args ]

**DESCRIPTION**

lvm fullreport produces formatted output about PVs, PV segments, VGs, LVs and LV segments.

The information is all gathered together for each VG (under a per-VG lock) so it is consistent. Information gathered from separate calls to vgs, pvs, and lvs can be inconsistent if information changes between commands.

**USAGE**

lvm fullreport

[ -a|--all ]

[ -o|--options String ]

[ -S|--select String ]

[ -O|--sort String ]

[ --aligned ]

[ --binary ]

[ --configreport log|vg|lv|pv|pvseg|seg ]

[ --foreign ]

[ --ignorelockingfailure ]

```
[ --logonly ]
[ --nameprefixes ]
[ --noheadings ]
[ --nosuffix ]
[ --readonly ]
[ --reportformat basic|json ]
[ --rows ]
[ --separator String ]
[ --shared ]
[ --unbuffered ]
[ --units r|R|h|H|b|B|s|S|k|K|m|M|g|G|t|T|p|P|e|E ]
[ --unquoted ]
[ COMMON_OPTIONS ]
[ VG ... ]
```

Common options for lvm:

```
[ -d|--debug ]
[ -h|--help ]
[ -q|--quiet ]
[ -t|--test ]
[ -v|--verbose ]
[ -y|--yes ]
[ --commandprofile String ]
[ --config String ]
[ --driverloaded y|n ]
[ --lockopt String ]
[ --longhelp ]
[ --nolocking ]
[ --profile String ]
[ --version ]
```

## OPTIONS

--aligned

Use with --separator to align the output columns

-a|--all

--binary

Use binary values "0" or "1" instead of descriptive literal values for columns that have exactly two valid values to report (not counting the "unknown" value which de? notes that the value could not be determined).

--commandprofile String

The command profile to use for command configuration. See lvm.conf(5) for more in? formation about profiles.

--config String

Config settings for the command. These override lvm.conf settings. The String arg uses the same format as lvm.conf, or may use section/field syntax. See lvm.conf(5) for more information about config.

--configreport log|vg|lv|pv|pvseg|seg

See lvmreport(7).

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

--foreign

Report/display foreign VGs that would otherwise be skipped. See lvmsystemid(7) for more information about foreign VGs.

-h|--help

Display help text.

--ignorelockingfailure

Allows a command to continue with read-only metadata operations after locking fail? ures.

--lockopt String

Used to pass options for special cases to lvmlockd. See lvmlockd(8) for more in? formation.

--logonly

Suppress command report and display only log report.

--longhelp

Display long help text.

--nameprefixes

Add an "LVM2\_" prefix plus the field name to the output. Useful with --noheadings to produce a list of field=value pairs that can be used to set environment variables (for example, in udev rules).

--noheadings

SUPPRESS the headings line that is normally the first line of output. Useful if grepping the output.

--nolocking

Disable locking.

--nosuffix

SUPPRESS the suffix on output sizes. Use with --units (except h and H) if process? ing the output.

-o|--options String

Comma-separated, ordered list of fields to display in columns. String arg syntax is: [+|-|#]Field1[,Field2 ...] The prefix + will append the specified fields to the default fields, - will remove the specified fields from the default fields, and # will compact specified fields (removing them when empty for all rows.) Use -h help to view the list of all available fields. Use separate lists of fields to add, remove or compact by repeating the -o option: -o+field1,field2 -o- field3,field4 -o#field5. These lists are evaluated from left to right. Use field name lv\_all to view all LV fields, vg\_all all VG fields, pv\_all all PV fields, pvseg\_all all PV segment fields, seg\_all all LV segment fields, and pvseg\_all all PV segment columns. See the lvm.conf report section for more config options. See lvmreport(7) for more information about reporting.

--profile String

An alias for --commandprofile or --metadataprofile, depending on the command.

-q|--quiet ...

SUPPRESS output and log messages. Overrides --debug and --verbose. Repeat once to also suppress any prompts with answer 'no'.

--readonly

Run the command in a special read-only mode which will read on-disk metadata without needing to take any locks. This can be used to peek inside metadata used by a

virtual machine image while the virtual machine is running. No attempt will be made to communicate with the device-mapper kernel driver, so this option is unable to report whether or not LVs are actually in use.

--reportformat basic|json

Overrides current output format for reports which is defined globally by the report/output\_format setting in lvm.conf. basic is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. json produces report output in JSON format. See lvmreport(7) for more information.

--rows

Output columns as rows.

-S|--select String

Select objects for processing and reporting based on specified criteria. The criteria syntax is described by --select help and lvmreport(7). For reporting commands, one row is displayed for each object matching the criteria. See --options help for selectable object fields. Rows can be displayed with an additional "selected" field (-o selected) showing 1 if the row matches the selection and 0 otherwise. For non-reporting commands which process LVM entities, the selection is used to choose items to process.

--separator String

String to use to separate each column. Useful if grepping the output.

--shared

Report/display shared VGs that would otherwise be skipped when lvmlockd is not being used on the host. See lvmlockd(8) for more information about shared VGs.

-O|--sort String

Comma-separated ordered list of columns to sort by. Replaces the default selection.

Precede any column with - for a reverse sort on that column.

-t|--test

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

--unbuffered

Produce output immediately without sorting or aligning the columns properly.

--units r|R|h|H|b|B|s|S|k|K|m|M|g|G|t|T|p|P|e|E

All sizes are output in these units: human-(r)eadable with '<' rounding indicator, (h)uman-readable, (b)ytes, (s)ectors, (k)ilobytes, (m)egabytes, (g)igabytes, (t)er? abytes, (p)etabytes, (e)xabytes. Capitalise to use multiples of 1000 (S.I.) instead of 1024. Custom units can be specified, e.g. --units 3M.

--unquoted

When used with --nameprefixes, output values in the field=value pairs are not quoted.

-v|--verbose ...

Set verbose level. Repeat from 1 to 4 times to increase the detail of messages sent to stdout and stderr.

--version

Display version information.

-y|--yes

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see -qq.)

## VARIABLES

VG

Volume Group name. See lvm(8) for valid names.

String

See the option description for information about the string content.

Size[UNIT]

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT.

UNIT represents other possible input units: bBsSkKmMgGtTpPeE. b|B is bytes, s|S is sectors of 512 bytes, k|K is KiB, m|M is MiB, g|G is GiB, t|T is TiB, p|P is PiB, e|E is EiB. (This should not be confused with the output control --units, where capital letters mean multiple of 1000.)

## ENVIRONMENT VARIABLES

See lvm(8) for information about environment variables used by lvm. For example, LVM\_VG\_NAME can generally be substituted for a required VG parameter.

## SEE ALSO

`lvm(8)` `lvm.conf(5)` `lvmconfig(8)`

`pvchange(8)` `pvck(8)` `pvcreate(8)` `pvdisplay(8)` `pvmove(8)` `pvremove(8)` `pvresize(8)` `pvs(8)` `pvs?(8)`

`vgcfgbackup(8)` `vgcfgrestore(8)` `vgchange(8)` `vgck(8)` `vgcreate(8)` `vgconvert(8)` `vgdisplay(8)`  
`vgexport(8)` `vgextend(8)` `vgimport(8)` `vgimportclone(8)` `vgmerge(8)` `vgmknodes(8)` `vgreduce(8)`  
`vgremove(8)` `vgrename(8)` `vgs(8)` `vgscan(8)` `vgsplit(8)`

`lvcreate(8)` `lvchange(8)` `lvconvert(8)` `lvdisplay(8)` `lvextend(8)` `lvreduce(8)` `lvremove(8)`

`lvrename(8)` `lvresize(8)` `lvs(8)` `lvscan(8)`

`lvm-fullreport(8)` `lvm-lvpoll(8)` `lvm2-activation-generator(8)` `blkdeactivate(8)` `lvmdump(8)`

`dmeventd(8)` `lvmpolld(8)` `lvmlockd(8)` `lvmlockctl(8)` `cmirrord(8)` `lvmdbusd(8)`

`lvmsystemid(7)` `lvmreport(7)` `lvmraid(7)` `lvmthin(7)` `lvmcache(7)`