



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'lvscan.8'

\$ man lvscan.8

LVSCAN(8)

System Manager's Manual

LVSCAN(8)

NAME

lvscan - List all logical volumes in all volume groups

SYNOPSIS

lvscan

[option_args]

DESCRIPTION

lvscan scans all VGs or all supported LVM block devices in the system for LVs. The output consists of one line for each LV indicating whether or not it is active, a snapshot or origin, the size of the device and its allocation policy. Use lvs(8) or lvdisplay(8) to obtain more comprehensive information about LVs.

USAGE

lvscan

[-a|--all]

[-b|--blockdevice]

[--ignorelockingfailure]

[--readonly]

[--reportformat basic|json]

[COMMON_OPTIONS]

Common options for lvm:

[-d|--debug]

[-h|--help]

[-q|--quiet]

```
[ -t|--test ]  
[ -v|--verbose ]  
[ -y|--yes ]  
[ --commandprofile String ]  
[ --config String ]  
[ --driverloaded y|n ]  
[ --lockopt String ]  
[ --longhelp ]  
[ --nolocking ]  
[ --profile String ]  
[ --version ]
```

OPTIONS

-a|--all

Show information about internal LVs. These are components of normal LVs, such as mirrors, which are not independently accessible, e.g. not mountable.

-b|--blockdevice

No longer used.

--commandprofile String

The command profile to use for command configuration. See lvm.conf(5) for more information about profiles.

--config String

Config settings for the command. These override lvm.conf settings. The String arg uses the same format as lvm.conf, or may use section/field syntax. See lvm.conf(5) for more information about config.

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

-h|--help

Display help text.

--ignorelockingfailure

Allows a command to continue with read-only metadata operations after locking fail? ures.

--lockopt String

Used to pass options for special cases to lvmlockd. See lvmlockd(8) for more information.

--longhelp

Display long help text.

--nolocking

Disable locking.

--profile String

An alias for --commandprofile or --metadaprofile, depending on the command.

-q|--quiet ...

Suppress output and log messages. Overrides --debug and --verbose. Repeat once to also suppress any prompts with answer 'no'.

--readonly

Run the command in a special read-only mode which will read on-disk metadata without needing to take any locks. This can be used to peek inside metadata used by a virtual machine image while the virtual machine is running. No attempt will be made to communicate with the device-mapper kernel driver, so this option is unable to report whether or not LVs are actually in use.

--reportformat basic|json

Overrides current output format for reports which is defined globally by the report/output_format setting in lvm.conf. basic is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. json produces report output in JSON format. See lvmreport(7) for more information.

-t|--test

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

-v|--verbose ...

Set verbose level. Repeat from 1 to 4 times to increase the detail of messages sent

to stdout and stderr.

--version

Display version information.

-y|--yes

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see -qq.)

VARIABLES

String

See the option description for information about the string content.

Size[UNIT]

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT.

UNIT represents other possible input units: b|Bs|Sk|Mg|Gt|Tp|Pe|E. b|B is bytes, s|S is sectors of 512 bytes, k|K is KiB, m|M is MiB, g|G is GiB, t|T is TiB, p|P is PiB, e|E is EiB. (This should not be confused with the output control --units, where capital letters mean multiple of 1000.)

ENVIRONMENT VARIABLES

See lvm(8) for information about environment variables used by lvm. For example,

LVM_VG_NAME can generally be substituted for a required VG parameter.

SEE ALSO

lvm(8) lvm.conf(5) lvmconfig(8)

pvchange(8) pvck(8) pvcreate(8) pvdisplay(8) pvmove(8) pvremove(8) pvresize(8) pvs(8) pvs?can(8)

vgcfgbackup(8) vgcfgrestore(8) vgchange(8) vgck(8) vgcreate(8) vgconvert(8) vgdisplay(8)
vgexport(8) vgextend(8) vgimport(8) vgimportclone(8) vgmerge(8) vgmknodes(8) vgreduce(8)
vgremove(8) vgrename(8) vgs(8) vgscan(8) vgsplit(8)

lvcreate(8) lvchange(8) lvconvert(8) lvdisplay(8) lvextend(8) lvreduce(8) lvremove(8)
lvrename(8) lvresize(8) lvs(8) lvscan(8)

lvm-fullreport(8) lvm-lvpoll(8) lvm2-activation-generator(8) blkdeactivate(8) lvmdump(8)
dmeventd(8) lvmpoll(8) lvmlockd(8) lvmlockctl(8) cmirrord(8) lvmdbusd(8)
lvmsystemid(7) lvmreport(7) lvmraid(7) lvmthin(7) lvmcache(7)