

non-existing partitions, so this option is possible to use together with large --nr ranges without care about the current partitions set on the device.

-g, --noheadings

Do not print a header line with --show or --raw.

-l, --list

List the partitions. Note that all numbers are in 512-byte sectors. This output format is DEPRECATED in favour of --show. Do not use it in newly written scripts.

-n, --nr M:N

Specify the range of partitions. For backward compatibility also the format M-N is supported. The range may contain negative numbers, for example --nr -1:-1 means the last partition, and --nr -2:-1 means the last two partitions. Supported range specifications are:

M

Specifies just one partition (e.g. --nr 3).

M:

Specifies the lower limit only (e.g. --nr 2:).

:N

Specifies the upper limit only (e.g. --nr :4).

M:N

Specifies the lower and upper limits (e.g. --nr 2:4).

-o, --output list

Define the output columns to use for --show, --pairs and --raw output. If no output arrangement is specified, then a default set is used. Use --help to get list of all supported columns. This option cannot be combined with the --add, --delete, --update or --list options.

--output-all

Output all available columns.

-P, --pairs

List the partitions using the KEY="value" format.

-r, --raw

List the partitions using the raw output format.

-s, --show

List the partitions. The output columns can be selected and rearranged with the

--output option. All numbers (except SIZE) are in 512-byte sectors.

-t, --type type

Specify the partition table type.

--list-types

List supported partition types and exit.

-u, --update

Update the specified partitions.

-S, --sector-size size

Overwrite default sector size.

-v, --verbose

Verbose mode.

-V, --version

Display version information and exit.

-h, --help

Display help text and exit.

ENVIRONMENT

LIBBLKID_DEBUG=all

enables libblkid debug output.

EXAMPLE

```
partx --show /dev/sdb3, partx --show --nr 3 /dev/sdb, partx --show /dev/sdb3 /dev/sdb
```

All three commands list partition 3 of /dev/sdb.

```
partx --show - /dev/sdb3
```

Lists all subpartitions on /dev/sdb3 (the device is used as whole-disk).

```
partx -o START -g --nr 5 /dev/sdb
```

Prints the start sector of partition 5 on /dev/sdb without header.

```
partx -o SECTORS,SIZE /dev/sda5 /dev/sda
```

Lists the length in sectors and human-readable size of partition 5 on /dev/sda.

```
partx --add --nr 3:5 /dev/sdd
```

Adds all available partitions from 3 to 5 (inclusive) on /dev/sdd.

```
partx -d --nr :-1 /dev/sdd
```

Removes the last partition on /dev/sdd.

AUTHORS

Davidlohr Bueso <dave@gnu.org>, Karel Zak <kzak@redhat.com>

The original version was written by Andries E. Brouwer <aeb@cwi.nl>

SEE ALSO

addpart(8), delpart(8), fdisk(8), parted(8), partprobe(8)

REPORTING BUGS

For bug reports, use the issue tracker at <https://github.com/karelzak/util-linux/issues>.

AVAILABILITY

The partx command is part of the util-linux package which can be downloaded from Linux

Kernel Archive <<https://www.kernel.org/pub/linux/utils/util-linux/>>.

util-linux 2.37.2

2021-06-02

PARTX(8)