



python



PowerShell

FPDF Library  
PDF generator

*Full credit is given to the above companies including the OS that this PDF file was generated!*

### **PowerShell Get-Help on command 'Get-NetAdapterSriov'**

**PS C:\Users\wahid> Get-Help Get-NetAdapterSriov**

#### NAME

Get-NetAdapterSriov

#### SYNOPSIS

Gets the SR-IOV properties of the network adapter.

#### SYNTAX

```
Get-NetAdapterSriov [-AsJob] [-CimSession <CimSession[]>] [-IncludeHidden]
-InterfaceDescription <String[]> [-ThrottleLimit <Int32>] [<CommonParameters>]
```

```
Get-NetAdapterSriov [[-Name] <String[]>] [-AsJob] [-CimSession <CimSession[]>]
[-IncludeHidden] [-ThrottleLimit <Int32>] [<CommonParameters>]
```

#### DESCRIPTION

The Get-NetAdapterSriov cmdlet gets the Single-Root I/O Virtualization (SR-IOV) properties of network adapters that support SR-IOV. SR-IOV enables network traffic to by-pass the software switch layer of the Hyper-V virtualization stack. As a result, the I/O overhead in the software emulation layer is diminished and can achieve network performance that is nearly the

same performance as in non-virtualized environments. Run this cmdlet to display how the hardware is set to support SR-IOV. This cmdlet will display the properties of the network adapter that relate to SR-IOV, such as the number of ports, and virtual functions (VFs). The property SrioVSupport indicates potential reasons for SR-IOV not functioning properly.

The possible values for SrioVSupport include the following:

- Unknown: Ensure that the computer has hardware support for SR-IOV and that I/O virtualization is enabled in the BIOS. Also ensure that the computer is running Windows Server 2012 and later.
- Supported: SR-IOV is supported and should be functioning properly.
- MissingAcs: SR-IOV cannot be used on this network adapter as the PCI Express hardware does not support Access Control Services (ACS).

This device may work in an alternate PCI Express slot. Contact your hardware vendor for further information.

- MissingPfDriver: SR-IOV cannot be used on this network adapter as the device or device driver does not support SR-IOV. If the network adapter supports SR-IOV, contact the hardware vendor for an updated driver.
- NoBusResources: SR-IOV cannot be used on this network adapter as there are not enough PCI Express bus numbers available.

- NoIoMmuSupport: SR-IOV cannot be used on this computer because of one or more of the following reasons.

- - The processor does not support second level address translation (SLAT).

For processors manufactured by Intel Corporation (Intel), this feature might be referred to as Extended Page Tables (EPT). For processors manufactured by Advanced Micro Devices (AMD), this feature might be referred to as Rapid Virtualization Indexing (RVI) or Nested Page Tables (NPT).

- - The chipset on the computer does not do Interrupt and/or DMA remapping, without which SR-IOV

cannot be supported.

- - This computer has been configured to disable the use of I/O remapping hardware.

- NoVfBarSpace: SR-IOV cannot be used on this network adapter as there are not enough PCI Express BAR resources available.

This may be due to incorrect or partial configuration in the computer BIOS for Interrupt and DMA remapping. These settings may be referred to as SR-IOV or input/output memory management unit (IOMMU) support. If the computer BIOS is correctly configured, this device may work in an alternate PCI Express slot.

Contact the original equipment manufacturer of the computer for further information. - NoOscSupport: To use SR-IOV on this computer, the computer BIOS must be updated to allow Windows Server 2012 and later to control PCI Express using `\_OSC HandOff`. Contact the original equipment manufacturer of the computer for an update.

## PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete. The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job completes. To manage the job, use the `\*-Job` cmdlets. To get the job results, use the Receive-Job (<https://go.microsoft.com/fwlink/?LinkID=113372>)cmdlet. For more information about Windows PowerShell background jobs, see about\_Jobs (<https://go.microsoft.com/fwlink/?LinkID=113251>).

-CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a New-CimSession

(<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or

[Get-CimSession](<https://go.microsoft.com/fwlink/p/?LinkId=227966>)cmdlet.

The default is the current session on the local computer.

**-IncludeHidden [<SwitchParameter>]**

Indicates that the cmdlet includes both visible and hidden network adapters in the operation. If a wildcard character is used to identify a network adapter, then the wildcard character is matched against both hidden and visible adapters.

**-InterfaceDescription <String[]>**

Specifies an array of network adapter interface descriptions. For a physical network adapter this is typically the name of the vendor of the network adapter followed by a part number and description, such as `Contoso 12345 Gigabit Network Device`.

**-Name <String[]>**

Specifies an array network adapter names. The name of the network adapter from which this cmdlet gets the SR-IOV properties.

**-ThrottleLimit <Int32>**

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit applies only to the current cmdlet, not to the session or to the computer.

**<CommonParameters>**

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (<https://go.microsoft.com/fwlink/?LinkID=113216>).

Example 1: Display SR-IOV properties for all SR-IOV-capable network adapters

```
PS C:\> Get-NetAdapterSriov -Name "**"
```

This command displays the SR-IOV properties for all SR-IOV-capable network adapters.

Example 2: Display SR-IOV properties for the specified network adapter

```
PS C:\> Get-NetAdapterSriov -Name "Ethernet 2"
```

This command displays the SR-IOV properties for network adapter named Ethernet 2.

Example 3: Display SR-IOV properties for the network adapter with the specified interface description

```
PS C:\> Get-NetAdapterSriov -InterfaceDescription "Contoso 12345 Gigabit Network Device"
```

This command displays the SR-IOV properties for the network adapter with the interface description named Contoso 12345 Gigabit Network Device.

Example 4: Get all SR-IOV properties for all network adapters with SR-IOV enabled

```
PS C:\> Get-NetAdapterSriov -Name "*" | Where-Object -FilterScript {  
$_.Enabled -Eq $true }
```

This command gets the SR-IOV properties for the network adapter with SR-IOV enabled.

## REMARKS

To see the examples, type: "get-help Get-NetAdapterSriov -examples".

For more information, type: "get-help Get-NetAdapterSriov -detailed".

For technical information, type: "get-help Get-NetAdapterSriov -full".

For online help, type: "get-help Get-NetAdapterSriov -online"