



Red Hat Enterprise Linux Release 9.2 Manual Pages on 'lvscan.8' command

\$ man lvscan.8

LVSCAN(8) System Manager's Manual LVSCAN(8)

NAME

lvscan ? List all logical volumes in all volume groups

SYNOPSIS

lvscan
[option_args]

DESCRIPTION

lvscan scans all VGs or all supported LVM block devices in the system for LVs. The output consists of one line for each LV indicating whether or not it is active, a snapshot or origin, the size of the device and its allocation policy. Use lvs(8) or lvdisplay(8) to obtain more comprehensive information about LVs.

USAGE

lvscan
[-a|--all]
[-b|--blockdevice]
[--ignorelockingfailure]
[--readonly]
[--reportformat basic|json|json_std]
[COMMON_OPTIONS]

Common options for lvm:

[-d|--debug]
[-h|--help]

[-q|--quiet]
[-t|--test]
[-v|--verbose]
[-y|--yes]
[--commandprofile String]
[--config String]
[--devices PV]
[--devicesfile String]
[--driverloaded y|n]
[--journal String]
[--lockopt String]
[--longhelp]
[--nohints]
[--nolocking]
[--profile String]
[--version]

OPTIONS

-a|--all

Show information about internal LVs. These are components of normal LVs, such as mirrors, which are not independently accessible, e.g. not mountable.

-b|--blockdevice

No longer used.

--commandprofile String

The command profile to use for command configuration. See `lvm.conf(5)` for more information about profiles.

--config String

Config settings for the command. These override `lvm.conf(5)` settings. The String arg uses the same format as `lvm.conf(5)`, or may use section/field syntax. See `lvm.conf(5)` for more information about config.

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail

of messages sent to the log file and/or syslog (if configured).

--devices PV

Restricts the devices that are visible and accessible to the command. Devices not listed will appear to be missing. This option can be repeated, or accepts a comma separated list of devices. This overrides the devices file.

--devicesfile String

A file listing devices that LVM should use. The file must exist in /etc/lvm/devices/ and is managed with the lvmdevices(8) command. This overrides the lvm.conf(5) devices/devicesfile and devices/use_devicesfile settings.

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

-h|--help

Display help text.

--ignorelockingfailure

Allows a command to continue with read-only metadata operations after locking failures.

--journal String

Record information in the systemd journal. This information is in addition to information enabled by the lvm.conf log/journal setting. command: record information about the command. output: record the default command output. debug: record full command debugging.

--lockopt String

Used to pass options for special cases to lvmlockd. See lvmlockd(8) for more information.

--longhelp

Display long help text.

--nohints

Do not use the hints file to locate devices for PVs. A command may read more devices to find PVs when hints are not used. The

command will still perform standard hint file invalidation where appropriate.

`--nolocking`

Disable locking. Use with caution, concurrent commands may produce incorrect results.

`--profile String`

An alias for `--commandprofile` or `--metadataprofile`, depending on the command.

`-q|--quiet ...`

Suppress output and log messages. Overrides `--debug` and `--verbose`. Repeat once to also suppress any prompts with answer 'no'.

`--readonly`

Run the command in a special read-only mode which will read on-disk metadata without needing to take any locks. This can be used to peek inside metadata used by a virtual machine image while the virtual machine is running. No attempt will be made to communicate with the device-mapper kernel driver, so this option is unable to report whether or not LVs are actually in use.

`--reportformat basic|json|json_std`

Overrides current output format for reports which is defined globally by the `report/output_format` setting in `lvm.conf(5)`. `basic` is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. `json` produces report output in JSON format. `json_std` produces report output in JSON format which is more compliant with JSON standard. See `lvmreport(7)` for more information.

`-t|--test`

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies

on reading back metadata it believes has changed but hasn't.

`-v|--verbose ...`

Set verbose level. Repeat from 1 to 4 times to increase the depth of messages sent to stdout and stderr.

`--version`

Display version information.

`-y|--yes`

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see `-qq`.)

VARIABLES

`String` See the option description for information about the string content.

`Size[UNIT]`

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT. UNIT represents other possible input units: b|B is bytes, s|S is sectors of 512 bytes, k|K is KiB, m|M is MiB, g|G is GiB, t|T is TiB, p|P is PiB, e|E is EiB. (This should not be confused with the output control `--units`, where capital letters mean multiple of 1000.)

ENVIRONMENT VARIABLES

See `lvm(8)` for information about environment variables used by `lvm`.

For example, `LVM_VG_NAME` can generally be substituted for a required `VG` parameter.

SEE ALSO

`lvm(8)`, `lvm.conf(5)`, `lvmconfig(8)`, `lvmdevices(8)`,
`pvchange(8)`, `pvck(8)`, `pvcreate(8)`, `pvdisplay(8)`, `pvmove(8)`,
`pvremove(8)`, `pvresize(8)`, `pvs(8)`, `pvscan(8)`,
`vgcfgbackup(8)`, `vgcfgrestore(8)`, `vgchange(8)`, `vgck(8)`, `vgcreate(8)`,
`vgconvert(8)`, `vgdisplay(8)`, `vgexport(8)`, `vgextend(8)`, `vgimport(8)`,

vgimportclone(8), vgimportdevices(8), vgmerge(8), vgmknodes(8),
vgreduce(8), vgrename(8), vgs(8), vgscan(8), vgsplit(8),
lvcreate(8), lvchange(8), lvconvert(8), lvdisplay(8), lvextend(8),
lvreduce(8), lvremove(8), lvrename(8), lvresize(8), lvs(8), lvscan(8),
lvm-fullreport(8), lvm-lvpoll(8), blkdeactivate(8), lvmdump(8),
dmeventd(8), lvmpolld(8), lvmlockd(8), lvmlockctl(8), cmirror(8),
lvmdbusd(8), fsadm(8),
lvmsystemid(7), lvmreport(7), lvmraid(7), lvmthin(7), lvmcache(7)

Red Hat, Inc.

LVM TOOLS 2.03.17(2) (2022-11-10)

LVSCAN(8)