



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'ptmx.4' command

\$ man ptmx.4

PTS(4) Linux Programmer's Manual PTS(4)

NAME

ptmx, pts - pseudoterminal master and slave

DESCRIPTION

The file `/dev/ptmx` (the pseudoterminal multiplexor device) is a character file with major number 5 and minor number 2, usually with mode 0666 and ownership `root:root`. It is used to create a pseudoterminal master and slave pair.

When a process opens `/dev/ptmx`, it gets a file descriptor for a pseudoterminal master and a pseudoterminal slave device is created in the `/dev/pts` directory. Each file descriptor obtained by opening `/dev/ptmx` is an independent pseudoterminal master with its own associated slave, whose path can be found by passing the file descriptor to `ptsname(3)`.

Before opening the pseudoterminal slave, you must pass the master's file descriptor to `grantpt(3)` and `unlockpt(3)`.

Once both the pseudoterminal master and slave are open, the slave provides processes with an interface that is identical to that of a real terminal.

Data written to the slave is presented on the master file descriptor as input. Data written to the master is presented to the slave as input.

In practice, pseudoterminals are used for implementing terminal emulators such as `xterm(1)`, in which data read from the pseudoterminal master is interpreted by the application in the same way a real terminal

would interpret the data, and for implementing remote-login programs such as sshd(8), in which data read from the pseudoterminal master is sent across the network to a client program that is connected to a terminal or terminal emulator.

Pseudoterminals can also be used to send input to programs that normally refuse to read input from pipes (such as su(1), and passwd(1)).

FILES

/dev/ptmx, /dev/pts/*

NOTES

The Linux support for the above (known as UNIX 98 pseudoterminal naming) is done using the devpts filesystem, which should be mounted on /dev/pts.

SEE ALSO

getpt(3), grantpt(3), ptsname(3), unlockpt(3), pty(7)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.