



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'user_contexts.5' command

\$ man user_contexts.5

user_contexts(5) SELinux configuration user_contexts(5)

NAME

user_contexts - The SELinux user contexts configuration files

DESCRIPTION

These optional user context configuration files contain entries that allow SELinux-aware login applications such as PAM(8) (running in their own process context), to determine the context that a user's session should run under.

SELinux-aware login applications generally use one or more of the following libselinux functions that read these files from the active policy path:

```
get_default_context(3)
get_ordered_context_list(3)
get_ordered_context_list_with_level(3)
get_default_context_with_level(3)
get_default_context_with_role(3)
get_default_context_with_rolelevel(3)
query_user_context(3)
manual_user_enter_context(3)
```

There can be one file for each SELinux user configured on the system.

The file path is formed using the path returned by `selinux_user_contexts_path(3)` for the active policy, with the SELinux user name appended, for example:

/etc/selinux/{SELINUXTYPE}/contexts/users/unconfined_u

/etc/selinux/{SELINUXTYPE}/contexts/users/xguest_u

Where {SELINUXTYPE} is the entry from the selinux configuration file config (see `selinux_config(5)`).

These files contain context information as described in the FILE FORMAT section.

FILE FORMAT

Each line in the user context configuration file consists of the following:

login_process user_login_process

Where:

login_process

This consists of a role:type[:range] entry that represents the login process context.

user_login_process

This consists of a role:type[:range] entry that represents the user login process context.

EXAMPLE

```
# Example for xguest_u at /etc/selinux/targeted/contexts/users/xguest_u

system_r:crond_t:s0      xguest_r:xguest_t:s0
system_r:initrc_t:s0      xguest_r:xguest_t:s0
system_r:local_login_t:s0  xguest_r:xguest_t:s0
system_r:remote_login_t:s0 xguest_r:xguest_t:s0
system_r:sshd_t:s0        xguest_r:xguest_t:s0
system_r:xdm_t:s0         xguest_r:xguest_t:s0
xguest_r:xguest_t:s0      xguest_r:xguest_t:s0
```

SEE ALSO

`selinux(8)`, `selinux_user_contexts_path(3)`, `PAM(8)`,
`get_ordered_context_list(3)`, `get_ordered_context_list_with_level(3)`,
`get_default_context_with_level(3)`, `get_default_context_with_role(3)`,
`get_default_context_with_rolelevel(3)`, `query_user_context(3)`,
`manual_user_enter_context(3)`, `selinux_config(5)`