



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'blkdeactivate.8'

\$ man blkdeactivate.8

BLKDEACTIVATE(8)

BLKDEACTIVATE(8)

NAME

blkdeactivate ? utility to deactivate block devices

SYNOPSIS

blkdeactivate [-d dm_options] [-e] [-h] [-l lvm_options] [-m
mpath_options] [-r mdraid_options] [-o vdo_options] [-u] [-v] [device]

DESCRIPTION

The blkdeactivate utility deactivates block devices. For mounted block devices, it attempts to unmount it automatically before trying to deactivate. The utility currently supports device-mapper devices (DM), including LVM volumes and software RAID MD devices. LVM volumes are handled directly using the lvm(8) command, the rest of device-mapper based devices are handled using the dmsetup(8) command. MD devices are handled using the mdadm(8) command.

OPTIONS

-d|--dmoptions dm_options

Comma separated list of device-mapper specific options. Accepted

dmsetup(8) options are:

retry Retry removal several times in case of failure.

force Force device removal.

-e|--errors

Show errors reported from tools called by blkdeactivate. Without this option, any error messages from these external tools are suppressed and the blkdeactivate itself provides only a summary message to indicate the device was skipped.

-h|--help

Display the help text.

-l|--lvmoptions lvm_options

Comma-separated list of LVM specific options:

retry Retry removal several times in case of failure.

wholevg

Deactivate the whole LVM Volume Group when processing a Logical Volume. Deactivating the Volume Group as a whole is quicker than deactivating each Logical Volume separately.

-r|--mdraidoptions mdraid_options

Comma-separated list of MD RAID specific options:

wait Wait MD device's resync, recovery or reshape action to complete before deactivation.

-m|--mpathoptions mpath_options

Comma-separated list of device-mapper multipath specific options:

disablequeueing

Disable queueing on all multipath devices before deactivation. This avoids a situation where blkdeactivate may end up waiting if all the paths are unavailable for any underlying device-mapper multipath device.

-o|--vdooptions vdo_options

Comma-separated list of VDO specific options:

configfile=file

Use specified VDO configuration file.

`-u|--umount`

Unmount a mounted device before trying to deactivate it. With? out this option used, a device that is mounted is not deactivat? ed.

`-v, --verbose`

Run in verbose mode. Use `-vv` for even more verbose mode.

EXAMPLES

Deactivate all supported block devices found in the system, skipping mounted devices.

```
# blkdeactivate
```

Deactivate all supported block devices found in the system, unmounting any mounted devices first, if possible.

```
# blkdeactivate -u
```

Deactivate the device `/dev/vg/lvol0` together with all its holders, un? mounting any mounted devices first, if possible.

```
# blkdeactivate -u /dev/vg/lvol0
```

Deactivate all supported block devices found in the system. If the de? activation of a device-mapper device fails, retry it. Deactivate the whole Volume Group at once when processing an LVM Logical Volume.

```
# blkdeactivate -u -d retry -l wholevg
```

Deactivate all supported block devices found in the system. If the de? activation of a device-mapper device fails, retry it and force removal.

```
# blkdeactivate -d force,retry
```

SEE ALSO

`dmsetup(8)`, `lsblk(8)`, `lvm(8)`, `mdadm(8)`, `multipathd(8)`, `vdo(8)`,
`umount(8)`

Red Hat, Inc LVM TOOLS 2.03.17(2) (2022-11-10) BLKDEACTIVATE(8)