

Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'dbus-run-session.1'

\$ man dbus-run-session.1

DBUS-RUN-SESSION(1)

User Commands

DBUS-RUN-SESSION(1)

NAME

dbus-run-session - start a process as a new D-Bus session

SYNOPSIS

dbus-run-session [--config-file FILENAME] [--dbus-daemon BINARY] [--]

PROGRAM [ARGUMENTS...]

dbus-run-session --help

dbus-run-session --version

DESCRIPTION

dbus-run-session is used to start a session bus instance of dbus-daemon from a shell script, and start a specified program in that session. The dbus-daemon will run for as long as the program does, after which it will terminate.

One use is to run a shell with its own dbus-daemon in a text?mode or SSH session, and have the dbus-daemon terminate automatically on leaving the sub?shell, like this:

dbus-run-session -- bash

or to replace the login shell altogether, by combining dbus-run-session

```
with the exec builtin:
    exec dbus-run-session -- bash
    Another use is to run regression tests and similar things in an
    isolated D-Bus session, to avoid either interfering with the "real"
    D-Bus session or relying on there already being a D-Bus session active,
    for instance:
    dbus-run-session -- make check
    or (in automake(1)):
       AM TESTS ENVIRONMENT = export MY DEBUG=all;
       LOG COMPILER = dbus-run-session
       AM LOG FLAGS = --
OPTIONS
    --config-file=FILENAME, --config-file FILENAME
      Pass --config-file=FILENAME to the bus daemon, instead of passing
      it the --session argument. See dbus-daemon(1).
    --dbus-daemon=BINARY, --dbus-daemon BINARY
      Run BINARY as dbus-daemon(1), instead of searching the PATH in the
      usual way for an executable called dbus-daemon.
    --help
      Print usage information and exit.
    --version
      Print the version of dbus-run-session and exit.
EXIT STATUS
    dbus-run-session exits with the exit status of PROGRAM, 0 if the --help
    or --version options were used, 127 on an error within dbus-run-session
    itself, or 128+n if the PROGRAM was killed by signal n.
ENVIRONMENT
    PATH is searched to find PROGRAM, and (if the --dbus-daemon option is
    not used or its argument does not contain a / character) to find
    dbus-daemon.
```

The session bus' address is made available to PROGRAM in the

The variables DBUS_SESSION_BUS_PID, DBUS_SESSION_BUS_WINDOWID,

environment variable DBUS_SESSION_BUS_ADDRESS.

Page 2/3

DBUS_STARTER_BUS_TYPE and DBUS_STARTER_ADDRESS are removed from the environment, if present.

BUGS

Please send bug reports to the D-Bus mailing list or bug tracker, see http://www.freedesktop.org/software/dbus/

SEE ALSO

dbus-daemon(1), dbus-launch(1)

D-Bus 1.12.20 06/12/2023 DBUS-RUN-SESSION(1)