



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'lvrename.8'***

**\$ man lvrename.8**

LVRENAME(8)            System Manager's Manual            LVRENAME(8)

NAME

lvrename ? Rename a logical volume

SYNOPSIS

lvrename position\_args

[ option\_args ]

DESCRIPTION

lvrename renames an existing LV or a historical LV (see lvremove for historical LV information.)

USAGE

lvrename VG LV LV\_new

[ COMMON\_OPTIONS ]

lvrename LV LV\_new

[ COMMON\_OPTIONS ]

Common options for command:

[ -A|--autobackup y|n ]

[ --noudevsync ]

[ --reportformat basic|json|json\_std ]

Common options for lvm:

- [ -d|--debug ]
- [ -h|--help ]
- [ -q|--quiet ]
- [ -t|--test ]
- [ -v|--verbose ]
- [ -y|--yes ]
- [ --commandprofile String ]
- [ --config String ]
- [ --devices PV ]
- [ --devicesfile String ]
- [ --driverloaded y|n ]
- [ --journal String ]
- [ --lockopt String ]
- [ --longhelp ]
- [ --nohints ]
- [ --nolocking ]
- [ --profile String ]
- [ --version ]

## OPTIONS

-A|--autobackup y|n

Specifies if metadata should be backed up automatically after a change. Enabling this is strongly advised! See [vgcfgbackup\(8\)](#) for more information.

--commandprofile String

The command profile to use for command configuration. See [lvm.conf\(5\)](#) for more information about profiles.

--config String

Config settings for the command. These override [lvm.conf\(5\)](#) settings. The String arg uses the same format as [lvm.conf\(5\)](#), or may use section/field syntax. See [lvm.conf\(5\)](#) for more information about config.

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

--devices PV

Restricts the devices that are visible and accessible to the command. Devices not listed will appear to be missing. This option can be repeated, or accepts a comma separated list of devices. This overrides the devices file.

--devicesfile String

A file listing devices that LVM should use. The file must exist in /etc/lvm/devices/ and is managed with the lvmdevices(8) command. This overrides the lvm.conf(5) devices/devicesfile and devices/use\_devicesfile settings.

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

-h|--help

Display help text.

--journal String

Record information in the systemd journal. This information is in addition to information enabled by the lvm.conf log/journal setting. command: record information about the command. output: record the default command output. debug: record full command debugging.

--lockopt String

Used to pass options for special cases to lvmlockd. See lvmlockd(8) for more information.

--longhelp

Display long help text.

--nohints

Do not use the hints file to locate devices for PVs. A command may read more devices to find PVs when hints are not used. The command will still perform standard hint file invalidation where appropriate.

--nolocking

Disable locking. Use with caution, concurrent commands may produce incorrect results.

--noudevsync

Disables udev synchronisation. The process will not wait for notification from udev. It will continue irrespective of any possible udev processing in the background. Only use this if udev is not running or has rules that ignore the devices LVM creates.

--profile String

An alias for --commandprofile or --metadataprofile, depending on the command.

-q|--quiet ...

Suppress output and log messages. Overrides --debug and --verbose. Repeat once to also suppress any prompts with answer 'no'.

--reportformat basic|json|json\_std

Overrides current output format for reports which is defined globally by the report/output\_format setting in lvm.conf(5). basic is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. json produces report output in JSON format. json\_std produces report output in JSON format which is more compliant with JSON standard. See lvmreport(7) for more information.

-t|--test

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

-v|--verbose ...

Set verbose level. Repeat from 1 to 4 times to increase the detail of messages sent to stdout and stderr.

--version

Display version information.

-y|--yes

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see -qq.)

## VARIABLES

**VG** Volume Group name. See `lvm(8)` for valid names.

**LV** Logical Volume name. See `lvm(8)` for valid names. An LV positional arg generally includes the VG name and LV name, e.g. VG/LV.

**String** See the option description for information about the string content.

**Size[UNIT]**

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT. UNIT represents other possible input units: b|B is bytes, s|S is sectors of 512 bytes, k|K is KiB, m|M is MiB, g|G is GiB, t|T is TiB, p|P is PiB, e|E is EiB. (This should not be confused with the output control --units, where capital letters mean multiple of 1000.)

## ENVIRONMENT VARIABLES

See `lvm(8)` for information about environment variables used by `lvm`.

For example, `LVM_VG_NAME` can generally be substituted for a required VG parameter.

## EXAMPLES

Rename "lvold" to "lvnew":

```
lvrename /dev/vg02/lvold vg02/lvnew
```

An alternate syntax to rename "lvold" to "lvnew":

```
lvrename vg02 lvold lvnew
```

## SEE ALSO

lvm(8), lvm.conf(5), lvmconfig(8), lvmdevices(8),  
pvchange(8), pvck(8), pvcreate(8), pvdisplay(8), pvmove(8),  
pvremove(8), pvresize(8), pvs(8), pvscan(8),  
vgcfgbackup(8), vgcfgrestore(8), vgchange(8), vgck(8), vgcreate(8),  
vgconvert(8), vgdisplay(8), vgexport(8), vgextend(8), vgimport(8),  
vgimportclone(8), vgimportdevices(8), vgmerge(8), vgmknodes(8),  
vgreduce(8), vgremove(8), vgrename(8), vgs(8), vgscan(8), vgsplit(8),  
lvcreate(8), lvchange(8), lvconvert(8), lvdisplay(8), lvextend(8),  
lvreduce(8), lvremove(8), lvrename(8), lvresize(8), lvs(8), lvscan(8),  
lvm-fullreport(8), lvm-lvpoll(8), blkdeactivate(8), lvmdump(8),  
dmeventd(8), lvmpolld(8), lvmlockd(8), lvmlockctl(8), cmirror(8),  
lvmdbusd(8), fsadm(8),  
lvmsystemid(7), lvmreport(7), lvmraid(7), lvmthin(7), lvmcache(7)

Red Hat, Inc.      LVM TOOLS 2.03.17(2) (2022-11-10)      LVRENAME(8)