



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'manpath.5'***

#### ***\$ man manpath.5***

MANPATH(5) /etc/man\_db.conf MANPATH(5)

#### NAME

manpath - format of the /etc/man\_db.conf file

#### DESCRIPTION

The manpath configuration file is used by the manual page utilities to assess users' manpaths at run time, to indicate which manual page hierarchies (manpaths) are to be treated as system hierarchies and to assign them directories to be used for storing cat files.

If the environment variable \$MANPATH is already set, the information contained within /etc/man\_db.conf will not override it.

#### FORMAT

The following field types are currently recognised:

# comment

Blank lines or those beginning with a # will be treated as comments and ignored.

MANDATORY\_MANPATH manpath\_element

Lines of this form indicate manpaths that every automatically generated \$MANPATH should contain. This will typically include

/usr/man.

MANPATH\_MAP path\_element manpath\_element

Lines of this form set up \$PATH to \$MANPATH mappings. For each path\_element found in the user's \$PATH, manpath\_element will be added to the \$MANPATH.

MANDB\_MAP manpath\_element [ catpath\_element ]

Lines of this form indicate which manpaths are to be treated as system manpaths, and optionally where their cat files should be stored. This field type is particularly important if man is a setuid program, as (when in the system configuration file /etc/man\_db.conf rather than the per-user configuration file .manpath) it indicates which manual page hierarchies to access as the setuid user and which as the invoking user.

The system manual page hierarchies are usually those stored under /usr such as /usr/man, /usr/local/man and /usr/X11R6/man.

If cat pages from a particular manpath\_element are not to be stored or are to be stored in the traditional location, catpath\_element may be omitted.

Traditional cat placement would be impossible for read only mounted manual page hierarchies and because of this it is possible to specify any valid directory hierarchy for their storage.

To observe the Linux FSSTND the keyword FSSTND can be used in place of an actual directory.

Unfortunately, it is necessary to specify all system man tree paths, including alternate operating system paths such as /usr/man/sun and any NLS locale paths such as /usr/man/de\_DE.88591.

As the information is parsed line by line in the order written, it is necessary for any manpath that is a sub-hierarchy of another hierarchy to be listed first, otherwise an incorrect match will be made. An example is that /usr/man/de\_DE.88591 must come before /usr/man.

DEFINE key value

Lines of this form define miscellaneous configuration variables; see the default configuration file for those variables used by the manual pager utilities. They include default paths to various programs (such as grep and tbl), and default sets of arguments to those programs.

#### SECTION section ...

Lines of this form define the order in which manual sections should be searched. If there are no SECTION directives in the configuration file, the default is:

```
SECTION 1 n l 8 3 0 2 5 4 9 6 7
```

If multiple SECTION directives are given, their section lists will be concatenated.

If a particular extension is not in this list (say, 1mh) it will be displayed with the rest of the section it belongs to. The effect of this is that you only need to explicitly list extensions if you want to force a particular order. Sections with extensions should usually be adjacent to their main section (e.g. "1 1mh 8 ...").

SECTIONS is accepted as an alternative name for this directive.

#### MINCATWIDTH width

If the terminal width is less than width, cat pages will not be created (if missing) or displayed. The default is 80.

#### MAXCATWIDTH width

If the terminal width is greater than width, cat pages will not be created (if missing) or displayed. The default is 80.

#### CATWIDTH width

If width is non-zero, cat pages will always be formatted for a terminal of the given width, regardless of the width of the terminal actually being used. This should generally be within the range set by MINCATWIDTH and MAXCATWIDTH.

#### NOCACHE

This flag prevents man(1) from creating cat pages automatically.

Unless the rules above are followed and observed precisely, the manual pager utilities will not function as desired. The rules are overly complicated.

<https://savannah.nongnu.org/bugs/?group=man-db>

2.9.3

2020-06-22

MANPATH(5)