



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'mq\_setattr.3'***

***\$ man mq\_setattr.3***

MQ\_GETATTR(3)          Linux Programmer's Manual          MQ\_GETATTR(3)

NAME

mq\_getattr, mq\_setattr - get/set message queue attributes

SYNOPSIS

```
#include <mqueue.h>

int mq_getattr(mqd_t mqdes, struct mq_attr *attr);

int mq_setattr(mqd_t mqdes, const struct mq_attr *newattr,
               struct mq_attr *oldattr);
```

Link with -lrt.

DESCRIPTION

mq\_getattr() and mq\_setattr() respectively retrieve and modify attributes of the message queue referred to by the message queue descriptor mqdes.

mq\_getattr() returns an mq\_attr structure in the buffer pointed by attr. This structure is defined as:

```
struct mq_attr {
    long mq_flags;     /* Flags: 0 or O_NONBLOCK */
    long mq_maxmsg;   /* Max. # of messages on queue */
```

```

long mq_msgsize; /* Max. message size (bytes) */
long mq_curmsgs; /* # of messages currently in queue */
};

```

The `mq_flags` field contains flags associated with the open message queue description. This field is initialized when the queue is created by `mq_open(3)`. The only flag that can appear in this field is `O_NONBLOCK`.

The `mq_maxmsg` and `mq_msgsize` fields are set when the message queue is created by `mq_open(3)`. The `mq_maxmsg` field is an upper limit on the number of messages that may be placed on the queue using `mq_send(3)`.

The `mq_msgsize` field is an upper limit on the size of messages that may be placed on the queue. Both of these fields must have a value greater than zero. Two `/proc` files that place ceilings on the values for these fields are described in `mq_overview(7)`.

The `mq_curmsgs` field returns the number of messages currently held in the queue.

`mq_setattr()` sets message queue attributes using information supplied in the `mq_attr` structure pointed to by `newattr`. The only attribute that can be modified is the setting of the `O_NONBLOCK` flag in `mq_flags`.

The other fields in `newattr` are ignored. If the `oldattr` field is not `NULL`, then the buffer that it points to is used to return an `mq_attr` structure that contains the same information that is returned by `mq_getattr()`.

## RETURN VALUE

On success `mq_getattr()` and `mq_setattr()` return 0; on error, -1 is returned, with `errno` set to indicate the error.

## ERRORS

**EBADF** The message queue descriptor specified in `mqdes` is invalid.

**EINVAL** `newattr->mq_flags` contained set bits other than `O_NONBLOCK`.

## ATTRIBUTES

For an explanation of the terms used in this section, see `attributes(7)`.

??

?Interface ? Attribute ? Value ?

??

?mq\_getattr(), mq\_setattr() ? Thread safety ? MT-Safe ?

??

CONFORMING TO

POSIX.1-2001, POSIX.1-2008.

NOTES

On Linux, mq\_getattr() and mq\_setattr() are library functions layered on top of the mq\_getsetattr(2) system call.

EXAMPLES

The program below can be used to show the default mq\_maxmsg and mq\_msgsize values that are assigned to a message queue that is created with a call to mq\_open(3) in which the attr argument is NULL. Here is an example run of the program:

```

$ ./a.out /testq

Maximum # of messages on queue: 10

Maximum message size:      8192
```

Since Linux 3.5, the following /proc files (described in mq\_overview(7)) can be used to control the defaults:

```

$ uname -sr

Linux 3.8.0

$ cat /proc/sys/fs/mqueue/msg_default

10

$ cat /proc/sys/fs/mqueue/msgsize_default

8192
```

Program source

```

#include <mqueue.h>

#include <sys/stat.h>

#include <fcntl.h>

#include <stdio.h>

#include <stdlib.h>

#include <unistd.h>

#define errExit(msg) do { perror(msg); exit(EXIT_FAILURE); \
```

```

        } while (0)

int
main(int argc, char *argv[])
{
    mqd_t mqd;
    struct mq_attr attr;
    if (argc != 2) {
        fprintf(stderr, "Usage: %s mq-name\n", argv[0]);
        exit(EXIT_FAILURE);
    }
    mqd = mq_open(argv[1], O_CREAT | O_EXCL, S_IRUSR | S_IWUSR, NULL);
    if (mqd == (mqd_t) -1)
        errExit("mq_open");
    if (mq_getattr(mqd, &attr) == -1)
        errExit("mq_getattr");
    printf("Maximum # of messages on queue: %ld\n", attr.mq_maxmsg);
    printf("Maximum message size: %ld\n", attr.mq_msgsize);
    if (mq_unlink(argv[1]) == -1)
        errExit("mq_unlink");
    exit(EXIT_SUCCESS);
}

```

#### SEE ALSO

mq\_close(3), mq\_notify(3), mq\_open(3), mq\_receive(3), mq\_send(3),  
mq\_unlink(3), mq\_overview(7)

#### COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.