



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'qemu-ga.8'***

**\$ man qemu-ga.8**

QEMU-GA(8) QEMU QEMU-GA(8)

#### **NAME**

qemu-ga - QEMU Guest Agent

#### **SYNOPSIS**

qemu-ga [OPTIONS]

#### **DESCRIPTION**

The QEMU Guest Agent is a daemon intended to be run within virtual machines. It allows the hypervisor host to perform various operations in

the guest, such as:

? get information from the guest

? set the guest's system time

? read/write a file

? sync and freeze the filesystems

? suspend the guest

? reconfigure guest local processors

? set user's password

? ...

qemu-ga will read a system configuration file on startup (located at

/etc/qemu-kvm/qemu-ga.conf by default), then parse remaining configuration options on the command line. For the same key, the last option wins, but the lists accumulate (see below for configuration file format).

## OPTIONS

**-m, --method=METHOD**

Transport method: one of unix-listen, virtio-serial, or isa-serial, or vsock-listen (virtio-serial is the default).

**-p, --path=PATH**

Device/socket path (the default for virtio-serial is /dev/virtio-ports/org.qemu.guest\_agent.0, the default for isa-serial is /dev/ttys0). Socket addresses for vsock-listen are written as <cid>:<port>.

**-l, --logfile=PATH**

Set log file path (default is stderr).

**-f, --pidfile=PATH**

Specify pid file (default is /var/run/qemu-ga.pid).

**-F, --fsfreeze-hook=PATH**

Enable fsfreeze hook. Accepts an optional argument that specifies script to run on freeze/thaw. Script will be called with 'freeze'/'thaw' arguments accordingly (default is /etc/qemu-kvm/fsfreeze-hook). If using -F with an argument, do not follow -F with a space (for example: -F/var/run/fsfreeze-hook.sh).

**-t, --statedir=PATH**

Specify the directory to store state information (absolute paths only, default is /var/run).

**-v, --verbose**

Log extra debugging information.

**-V, --version**

Print version information and exit.

**-d, --daemon**

Daemonize after startup (detach from terminal).

**-b, --block-rpcs=LIST**

Comma-separated list of RPCs to disable (no spaces, use help to list available RPCs).

**-D, --dump-conf**

Dump the configuration in a format compatible with `qemu-ga.conf` and exit.

**-h, --help**

Display this help and exit.

## FILES

The syntax of the `qemu-ga.conf` configuration file follows the Desktop Entry Specification, here is a quick summary: it consists of groups of key-value pairs, interspersed with comments.

```
# qemu-ga configuration sample

[general]

daemonize = 0

pidfile = /var/run/qemu-ga.pid

verbose = 0

method = virtio-serial

path = /dev/virtio-ports/org.qemu.guest_agent.0

statedir = /var/run
```

The list of keys follows the command line options:

```
?????????????????????????????????????????  
?Key      ? Key type  ?  
?????????????????????????????????????????  
?daemon    ? boolean   ?  
?????????????????????????????????????????  
?method    ? string    ?  
?????????????????????????????????????????  
?path      ? string    ?  
?????????????????????????????????????????  
?logfile   ? string    ?  
?????????????????????????????????????????  
?pidfile  ? string    ?
```

```
?fsfreeze-hook ? string      ?  
?????????????????????????????  
?statedir    ? string      ?  
?????????????????????????????  
?verbose     ? boolean      ?  
?????????????????????????????  
?block-rpcs   ? string list ?  
?????????????????????????????
```

## SEE ALSO

[qemu\(1\)](#)

## AUTHOR

Michael Roth <[mdroth@linux.vnet.ibm.com](mailto:mdroth@linux.vnet.ibm.com)>

## COPYRIGHT

2023, The QEMU Project Developers

7.2.0

May 25, 2023

QEMU-GA(8)