



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'quotaoff.8'***

***\$ man quotaoff.8***

QUOTAON(8)                    System Manager's Manual                    QUOTAON(8)

NAME

quotaon, quotaoff - turn filesystem quotas on and off

SYNOPSIS

quotaon [ -vugfp ] [ -F format-name ] filesystem...

quotaon [ -avugPfp ] [ -F format-name ]

quotaoff [ -vugPp ] [ -x state ] filesystem...

quotaoff [ -avugp ]

DESCRIPTION

quotaon

quotaon announces to the system that disk quotas should be enabled on one or more filesystems. The filesystem quota files must be present in the root directory of the specified filesystem and be named either aquota.user (for version 2 user quota), quota.user (for version 1 user quota), aquota.group (for version 2 group quota), or quota.group (for version 1 group quota).

XFS filesystems are a special case - XFS considers quota information as filesystem metadata and uses journaling to provide a higher level guar?

antee of consistency. There are two components to the XFS disk quota system: accounting and limit enforcement. XFS filesystems require that quota accounting be turned on at mount time. It is possible to enable and disable limit enforcement on an XFS filesystem after quota accounting is already turned on. The default is to turn on both accounting and enforcement.

The XFS quota implementation does not maintain quota information in user-visible files, but rather stores this information internally.

#### quotaoff

quotaoff announces to the system that the specified filesystems should have any disk quotas turned off.

### OPTIONS

#### quotaon

-F, --format=format-name

Report quota for specified format (ie. don't perform format autodetection). Possible format names are: vfsold Original quota format with 16-bit UIDs / GIDs, vfst0 Quota format with 32-bit UIDs / GIDs, 64-bit space usage, 32-bit inode usage and limits, vfst1 Quota format with 64-bit quota limits and usage, xfs (quota on XFS filesystem)

-a, --all

All automatically mounted (no noauto option) non-NFS filesystems in /etc/fstab with quotas will have their quotas turned on.

This is normally used at boot time to enable quotas.

-v, --verbose

Display a message for each filesystem where quotas are turned on.

-u, --user

Manipulate user quotas. This is the default.

-g, --group

Manipulate group quotas.

-P, --project

Manipulate project quotas.

-p, --print-state

Instead of turning quotas on just print state of quotas (ie. whether. quota is on or off)

-x, --xfs-command enforce

Switch on limit enforcement for XFS filesystems. This is the default action for any XFS filesystem. This option is only applicable to XFS, and is silently ignored for other filesystem types.

-f, --off

Make quotaon behave like being called as quotaoff.

quotaoff

-F, --format=format-name

Report quota for specified format (ie. don't perform format autodetection). Possible format names are: vfsold (version 1 quota), vfstv0 (version 2 quota), xfs (quota on XFS filesystem)

-a, --all

Force all filesystems in /etc/fstab to have their quotas disabled.

-v, --verbose

Display a message for each filesystem affected.

-u, --user

Manipulate user quotas. This is the default.

-g, --group

Manipulate group quotas.

-P, --project

Manipulate project quotas.

-p, --print-state

Instead of turning quotas off just print state of quotas (ie. whether. quota is on or off)

-x, --xfs-command delete

Free up the space used to hold quota information (maintained internally) within XFS. This option is only applicable to XFS, and is silently ignored for other filesystem types. It can only

be used on a filesystem with quota previously turned off.

-x, --xfs-command enforce

Switch off limit enforcement for XFS filesystems (perform quota accounting only). This is the default action for any XFS filesystem. This option is only applicable to XFS, and is silently ignored for other filesystem types.

-x, --xfs-command account

This option can be used to disable quota accounting. It is not possible to enable quota accounting by quota tools. Use mount(8) for that. This option is only applicable to XFS filesystems, and is silently ignored for other filesystem types.

## NOTES ON XFS FILESYSTEMS

To enable quotas on an XFS filesystem, use mount(8) or /etc/fstab quota option to enable both accounting and limit enforcement. quotaon utility cannot be used for this purpose.

Turning on quotas on an XFS root filesystem requires the quota mount options be passed into the kernel at boot time through the Linux root? flags boot option.

To turn off quota limit enforcement on any XFS filesystem, first make sure that quota accounting and enforcement are both turned on using repquota -v filesystem. Then, use quotaoff -v filesystem to disable limit enforcement. This may be done while the filesystem is mounted.

Turning on quota limit enforcement on an XFS filesystem is achieved using quotaon -v filesystem. This may be done while the filesystem is mounted.

## FILES

aquota.user or aquota.group

quota file at the filesystem root (version 2 quota, non-XFS filesystems)

quota.user or quota.group

quota file at the filesystem root (version 1 quota, non-XFS filesystems)

/etc/fstab default filesystems

SEE ALSO

quotactl(2), fstab(5), quota\_nld(8), repquota(8), warnquota(8)

4th Berkeley Distribution

QUOTAON(8)