



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'semanage-node.8'***

**\$ man semanage-node.8**

semanage-node(8) semanage-node(8)

#### NAME

semanage-node - SELinux Policy Management node mapping tool

#### SYNOPSIS

```
semanage node [-h] [-n] [-N] [-S STORE] [ --add -M NETMASK -p PROTOCOL
-t TYPE -r RANGE node | --delete -M NETMASK -p PROTOCOL node |
--deleteall | --extract | --list [-C] | --modify -M NETMASK -p PROTOCOL
-t TYPE -r RANGE node ]
```

#### DESCRIPTION

semanage is used to configure certain elements of SELinux policy with? out requiring modification to or recompilation from policy sources. semanage controls the ipaddress to node type definitions.

#### OPTIONS

- h, --help  
show this help message and exit
- n, --noheading  
Do not print heading when listing the specified object type
- N, --noreload

Do not reload policy after commit

-S STORE, --store STORE

Select an alternate SELinux Policy Store to manage

-C, --locallist

List local customizations

-a, --add

Add a record of the specified object type

-d, --delete

Delete a record of the specified object type

-m, --modify

Modify a record of the specified object type

-l, --list

List records of the specified object type

-E, --extract

Extract customizable commands, for use within a transaction

-D, --deleteall

Remove all local customizations

-M NETMASK, --netmask NETMASK

Network Mask, either in CIDR (/16) or address mask notation

(255.255.0.0, ffff::)

-t TYPE, --type TYPE

SELinux type for the object

-r RANGE, --range RANGE

MLS/MCS Security Range (MLS/MCS Systems only) SELinux Range for

SELinux login mapping defaults to the SELinux user record range.

SELinux Range for SELinux user defaults to s0.

-p PROTO, --proto PROTO

Protocol for the specified port (tcp|udp) or internet protocol

version for the specified node (ipv4|ipv6).

20130617

semanage-node(8)