



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'vgcfgbackup.8'***

**\$ man vgcfgbackup.8**

VGCFGBACKUP(8)      System Manager's Manual      VGCFGBACKUP(8)

NAME

vgcfgbackup ? Backup volume group configuration(s)

SYNOPSIS

vgcfgbackup

[ option\_args ]

[ position\_args ]

DESCRIPTION

vgcfgbackup creates back up files containing metadata of VGs. If no VGs are named, back up files are created for all VGs. See vgcfgrestore for information on using the back up files.

In a default installation, each VG is backed up into a separate file bearing the name of the VG in the directory /etc/lvm/backup.

To use an alternative back up file, use -f. In this case, when backing up multiple VGs, the file name is treated as a template, with %s replaced by the VG name.

NB. This DOES NOT back up the data content of LVs.

It may also be useful to regularly back up the files in /etc/lvm.

## USAGE

vgcfgbackup

[ -f|--file String ]

[ --foreign ]

[ --ignorelockingfailure ]

[ --readonly ]

[ --reportformat basic|json|json\_std ]

[ COMMON\_OPTIONS ]

[ VG ... ]

Common options for lvm:

[ -d|--debug ]

[ -h|--help ]

[ -q|--quiet ]

[ -t|--test ]

[ -v|--verbose ]

[ -y|--yes ]

[ --commandprofile String ]

[ --config String ]

[ --devices PV ]

[ --devicesfile String ]

[ --driverloaded y|n ]

[ --journal String ]

[ --lockopt String ]

[ --longhelp ]

[ --nohints ]

[ --nolocking ]

[ --profile String ]

[ --version ]

## OPTIONS

--commandprofile String

The command profile to use for command configuration. See `lvm.conf(5)` for more information about profiles.

--config String

Config settings for the command. These override `lvm.conf(5)` settings. The String arg uses the same format as `lvm.conf(5)`, or may use section/field syntax. See `lvm.conf(5)` for more information about config.

`-d|--debug ...`

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

`--devices PV`

Restricts the devices that are visible and accessible to the command. Devices not listed will appear to be missing. This option can be repeated, or accepts a comma separated list of devices. This overrides the devices file.

`--devicesfile String`

A file listing devices that LVM should use. The file must exist in `/etc/lvm/devices/` and is managed with the `lvmdevices(8)` command. This overrides the `lvm.conf(5)` `devices/devicesfile` and `devices/use_devicesfile` settings.

`--driverloaded y|n`

If set to no, the command will not attempt to use device-mapper.

For testing and debugging.

`-f|--file String`

Write the backup to the named file. When backing up more than one VG, the file name is treated as a template, and `%s` is replaced by the VG name.

`--foreign`

Report/display foreign VGs that would otherwise be skipped. See `lvmsystemid(7)` for more information about foreign VGs.

`-h|--help`

Display help text.

`--ignorelockingfailure`

Allows a command to continue with read-only metadata operations after locking failures.

`--journal String`

Record information in the systemd journal. This information is in addition to information enabled by the `lvm.conf log/journal` setting. `command`: record information about the command. `output`: record the default command output. `debug`: record full command debugging.

`--lockopt` String

Used to pass options for special cases to `lvmlockd`. See `lvmlockd(8)` for more information.

`--longhelp`

Display long help text.

`--nohints`

Do not use the hints file to locate devices for PVs. A command may read more devices to find PVs when hints are not used. The command will still perform standard hint file invalidation where appropriate.

`--nolocking`

Disable locking. Use with caution, concurrent commands may produce incorrect results.

`--profile` String

An alias for `--commandprofile` or `--metadataprofile`, depending on the command.

`-q|--quiet` ...

Suppress output and log messages. Overrides `--debug` and `--verbose`. Repeat once to also suppress any prompts with answer 'no'.

`--readonly`

Run the command in a special read-only mode which will read on-disk metadata without needing to take any locks. This can be used to peek inside metadata used by a virtual machine image while the virtual machine is running. No attempt will be made to communicate with the device-mapper kernel driver, so this option is unable to report whether or not LVs are actually in use.

`--reportformat` basic|json|json\_std

Overrides current output format for reports which is defined globally by the `report/output_format` setting in `lvm.conf(5)`. `basic` is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. `json` produces report output in JSON format. `json_std` produces report output in JSON format which is more compliant with JSON standard. See `lvmreport(7)` for more information.

`-t|--test`

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

`-v|--verbose ...`

Set verbose level. Repeat from 1 to 4 times to increase the default tail of messages sent to stdout and stderr.

`--version`

Display version information.

`-y|--yes`

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see `-qq`.)

## VARIABLES

`VG` Volume Group name. See `lvm(8)` for valid names.

`String` See the option description for information about the string content.

`Size[UNIT]`

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT. UNIT represents other possible input units: b|B is bytes, s|S is sectors

of 512 bytes, k|K is KiB, m|M is MiB, g|G is GiB, t|T is TiB, p|P is PiB, e|E is EiB. (This should not be confused with the output control `--units`, where capital letters mean multiple of 1000.)

## ENVIRONMENT VARIABLES

See `lvm(8)` for information about environment variables used by `lvm`.

For example, `LVM_VG_NAME` can generally be substituted for a required `VG` parameter.

## SEE ALSO

`lvm(8)`, `lvm.conf(5)`, `lvmconfig(8)`, `lvmdevices(8)`,  
`pvchange(8)`, `pvck(8)`, `pvcreate(8)`, `pvdisplay(8)`, `pvmove(8)`,  
`pvremove(8)`, `pvresize(8)`, `pvs(8)`, `pvscan(8)`,  
`vgcfgbackup(8)`, `vgcfgrestore(8)`, `vgchange(8)`, `vgck(8)`, `vgcreate(8)`,  
`vgconvert(8)`, `vgdisplay(8)`, `vgexport(8)`, `vgextend(8)`, `vgimport(8)`,  
`vgimportclone(8)`, `vgimportdevices(8)`, `vgmerge(8)`, `vgmknodes(8)`,  
`vgreduce(8)`, `vgremove(8)`, `vgrename(8)`, `vgs(8)`, `vgscan(8)`, `vgsplit(8)`,  
`lvcreate(8)`, `lvchange(8)`, `lvconvert(8)`, `lvdisplay(8)`, `lvextend(8)`,  
`lvreduce(8)`, `lvremove(8)`, `lvrename(8)`, `lvresize(8)`, `lvs(8)`, `lvscan(8)`,  
`lvm-fullreport(8)`, `lvm-lvpoll(8)`, `blkdeactivate(8)`, `lvmdump(8)`,  
`dmeventd(8)`, `lvmpolld(8)`, `lvmlockd(8)`, `lvmlockctl(8)`, `cmirror(8)`,  
`lvmdbusd(8)`, `fsadm(8)`,  
`lvmsystemid(7)`, `lvmreport(7)`, `lvraid(7)`, `lvthin(7)`, `lvmdcache(7)`

Red Hat, Inc.      LVM TOOLS 2.03.17(2) (2022-11-10)      `VGCFGBACKUP(8)`