



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'vgimport.8'***

**\$ man vgimport.8**

VGIMPORT(8) System Manager's Manual VGIMPORT(8)

#### NAME

vgimport ? Register exported volume group with system

#### SYNOPSIS

vgimport option\_args position\_args

[ option\_args ]

#### DESCRIPTION

vgimport makes exported VGs known to the system again, perhaps after moving the PVs from a different system.

vgexport clears the VG system ID, and vgimport sets the VG system ID to match the host running vgimport (if the host has a system ID).

#### USAGE

Import specified VGs.

vgimport VG|Tag|Select ...

[ -S|--select String ]

[ COMMON\_OPTIONS ]

Import all VGs.

vgimport -a|--all

[ COMMON\_OPTIONS ]

Common options for command:

[ -f|--force ]

[ --reportformat basic|json|json\_std ]

Common options for lvm:

[ -d|--debug ]

[ -h|--help ]

[ -q|--quiet ]

[ -t|--test ]

[ -v|--verbose ]

[ -y|--yes ]

[ --commandprofile String ]

[ --config String ]

[ --devices PV ]

[ --devicesfile String ]

[ --driverloaded y|n ]

[ --journal String ]

[ --lockopt String ]

[ --longhelp ]

[ --nohints ]

[ --nolocking ]

[ --profile String ]

[ --version ]

## OPTIONS

-a|--all

Import all visible VGs.

--commandprofile String

The command profile to use for command configuration. See `lvm.conf(5)` for more information about profiles.

--config String

Config settings for the command. These override `lvm.conf(5)` settings. The String arg uses the same format as `lvm.conf(5)`, or may use section/field syntax. See `lvm.conf(5)` for more informa?

tion about config.

`-d|--debug ...`

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

`--devices PV`

Restricts the devices that are visible and accessible to the command. Devices not listed will appear to be missing. This option can be repeated, or accepts a comma separated list of devices. This overrides the devices file.

`--devicesfile String`

A file listing devices that LVM should use. The file must exist in `/etc/lvm/devices/` and is managed with the `lvmdevices(8)` command. This overrides the `lvm.conf(5)` `devices/devicesfile` and `devices/use_devicesfile` settings.

`--driverloaded y|n`

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

`-f|--force ...`

Override various checks, confirmations and protections. Use with extreme caution.

`-h|--help`

Display help text.

`--journal String`

Record information in the systemd journal. This information is in addition to information enabled by the `lvm.conf` `log/journal` setting. `command`: record information about the command. `output`: record the default command output. `debug`: record full command debugging.

`--lockopt String`

Used to pass options for special cases to `lvmlockd`. See `lvmlockd(8)` for more information.

`--longhelp`

Display long help text.

--nohints

Do not use the hints file to locate devices for PVs. A command may read more devices to find PVs when hints are not used. The command will still perform standard hint file invalidation where appropriate.

--nolocking

Disable locking. Use with caution, concurrent commands may produce incorrect results.

--profile String

An alias for --commandprofile or --metadataprofile, depending on the command.

-q|--quiet ...

Suppress output and log messages. Overrides --debug and --verbose. Repeat once to also suppress any prompts with answer 'no'.

--reportformat basic|json|json\_std

Overrides current output format for reports which is defined globally by the report/output\_format setting in lvm.conf(5). basic is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. json produces report output in JSON format. json\_std produces report output in JSON format which is more compliant with JSON standard. See lvmreport(7) for more information.

-S|--select String

Select objects for processing and reporting based on specified criteria. The criteria syntax is described by --select help and lvmreport(7). For reporting commands, one row is displayed for each object matching the criteria. See --options help for selectable object fields. Rows can be displayed with an additional "selected" field (-o selected) showing 1 if the row matches the selection and 0 otherwise. For non-reporting commands which process LVM entities, the selection is used to

choose items to process.

`-t|--test`

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

`-v|--verbose ...`

Set verbose level. Repeat from 1 to 4 times to increase the default of messages sent to stdout and stderr.

`--version`

Display version information.

`-y|--yes`

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see `-qq`.)

## VARIABLES

`VG` Volume Group name. See `lvm(8)` for valid names.

`Tag` Tag name. See `lvm(8)` for information about tag names and using tags in place of a VG, LV or PV.

`Select` `Select` indicates that a required positional parameter can be omitted if the `--select` option is used. No arg appears in this position.

`String` See the option description for information about the string content.

`Size[UNIT]`

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT. UNIT represents other possible input units: b|B is bytes, s|S is sectors of 512 bytes, k|K is KiB, m|M is MiB, g|G is GiB, t|T is TiB, p|P is PiB, e|E is EiB. (This should not be confused with the

output control --units, where capital letters mean multiple of 1000.)

## ENVIRONMENT VARIABLES

See `lvm(8)` for information about environment variables used by `lvm`.

For example, `LVM_VG_NAME` can generally be substituted for a required `VG` parameter.

## SEE ALSO

`lvm(8)`, `lvm.conf(5)`, `lvmconfig(8)`, `lvmdevices(8)`,  
`pvchange(8)`, `pvck(8)`, `pvcreate(8)`, `pvdisplay(8)`, `pvmove(8)`,  
`pvremove(8)`, `pvresize(8)`, `pvs(8)`, `pvscan(8)`,  
`vgcfgbackup(8)`, `vgcfgrestore(8)`, `vgchange(8)`, `vgck(8)`, `vgcreate(8)`,  
`vgconvert(8)`, `vgdisplay(8)`, `vgexport(8)`, `vgextend(8)`, `vgimport(8)`,  
`vgimportclone(8)`, `vgimportdevices(8)`, `vgmerge(8)`, `vgmknodes(8)`,  
`vgreduce(8)`, `vgremove(8)`, `vgrename(8)`, `vgs(8)`, `vgscan(8)`, `vgsplit(8)`,  
`lvcreate(8)`, `lvchange(8)`, `lvconvert(8)`, `lvdisplay(8)`, `lvextend(8)`,  
`lvreduce(8)`, `lvremove(8)`, `lvrename(8)`, `lvresize(8)`, `lvs(8)`, `lvscan(8)`,  
`lvm-fullreport(8)`, `lvm-lvpoll(8)`, `blkdeactivate(8)`, `lvmdump(8)`,  
`dmeventd(8)`, `lvmpolld(8)`, `lvmlockd(8)`, `lvmlockctl(8)`, `cmirror(8)`,  
`lvmdbusd(8)`, `fsadm(8)`,  
`lvmsystemid(7)`, `lvmreport(7)`, `lvraid(7)`, `lvthin(7)`, `lvmdcache(7)`

Red Hat, Inc.      LVM TOOLS 2.03.17(2) (2022-11-10)      VGIMPORT(8)