



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'yum-copr.8'

\$ man yum-copr.8

YUM-COPR(8) dnf-plugins-core YUM-COPR(8)

NAME

yum-copr - redirecting to DNF copr Plugin

Work with Copr & Playground repositories on the local system.

? The copr command is used to add or remove Copr repositories to the local system

? The playground is used to enable or disable the Playground repository

SYNOPSIS

dnf copr [enable|disable|remove|list|search] <parameters>

dnf playground [enable|disable|upgrade]

ARGUMENTS (COPR)

enable name/project [chroot]

Enable the name/project Copr repository with the optional ch? root.

disable name/project

Disable the name/project Copr repository.

remove name/project

Remove the name/project Copr repository.

list --installed
List installed Copr repositories (default).

list --enabled
List enabled Copr repositories.

list --disabled
List disabled Copr repositories.

list --available-by-user=name
List available Copr repositories for a given name.

search project
Search for a given project.

enable hub/name/project
Enable the name/project Copr repository from the specified Copr hub, Hub is be specified either by its hostname (eg. copr.fedorainfracloud.org) or by an ID that's defined in a configuration file.

OPTIONS (COPR)

All general DNF options are accepted, see Options in dnf(8) for details.

--hub Copr
Specify a Copr hub to use. Default is the Fedora Copr:
<https://copr.fedorainfracloud.org>.

CONFIGURATION (COPR)

/etc/dnf/plugins/coprc.conf /etc/dnf/plugins/coprd/

Configuration file should contain a section for each hub, each section having hostname

(mandatory), protocol (default https) and port (default 443) parameters.:

```
[fedora]
hostname = copr.fedorainfracloud.org
protocol = https
port = 443
```

ARGUMENTS (PLAYGROUND)

enable Enable the Playground repository.

disable

Disable the Playground repository.

upgrade

Upgrade the Playground repository settings (same as disable and then enable).

OPTIONS (PLAYGROUND)

All general DNF options are accepted, see Options in dnf(8) for details.

EXAMPLES

```
copr enable rhscl/perl516 epel-6-x86_64
```

Enable the rhscl/perl516 Copr repository, using the epel-6-x86_64 chroot.

```
copr disable rhscl/perl516
```

Disable the rhscl/perl516 Copr repository

```
copr list --available-by-user=rita
```

List available Copr projects for user rita.

```
copr search tests
```

Search for Copr projects named tests.

AUTHOR

See AUTHORS in your Core DNF Plugins distribution

COPYRIGHT

2023, Red Hat, Licensed under GPLv2+

4.3.0

Mar 15, 2023

YUM-COPR(8)