

NAME

`iconv_open` – allocate descriptor for character set conversion

SYNOPSIS

```
#include <iconv.h>
```

```
iconv_t iconv_open(const char *tocode, const char *fromcode);
```

DESCRIPTION

The `iconv_open()` function allocates a conversion descriptor suitable for converting byte sequences from character encoding *fromcode* to character encoding *tocode*.

The values permitted for *fromcode* and *tocode* and the supported combinations are system-dependent. For the GNU C library, the permitted values are listed by the `iconv --list` command, and all combinations of the listed values are supported. Furthermore the GNU C library and the GNU libiconv library support the following two suffixes:

```
//TRANSLIT
```

When the string `//TRANSLIT` is appended to *tocode*, transliteration is activated. This means that when a character cannot be represented in the target character set, it can be approximated through one or several similarly looking characters.

```
//IGNORE
```

When the string `//IGNORE` is appended to *tocode*, characters that cannot be represented in the target character set will be silently discarded.

The resulting conversion descriptor can be used with `iconv(3)` any number of times. It remains valid until deallocated using `iconv_close(3)`.

A conversion descriptor contains a conversion state. After creation using `iconv_open()`, the state is in the initial state. Using `iconv(3)` modifies the descriptor's conversion state. To bring the state back to the initial state, use `iconv(3)` with `NULL` as *inbuf* argument.

RETURN VALUE

The `iconv_open()` function returns a freshly allocated conversion descriptor. In case of error, it sets *errno* and returns `(iconv_t) -1`.

ERRORS

The following error can occur, among others:

EINVAL

The conversion from *fromcode* to *tocode* is not supported by the implementation.

VERSIONS

This function is available in glibc since version 2.1.

ATTRIBUTES

For an explanation of the terms used in this section, see `attributes(7)`.

Interface	Attribute	Value
<code>iconv_open()</code>	Thread safety	MT-Safe locale

CONFORMING TO

POSIX.1-2001, POSIX.1-2008, SUSv2.

SEE ALSO

`iconv(1)`, `iconv(3)`, `iconv_close(3)`

COLOPHON

This page is part of release 5.05 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.