NAME

netdevice – low-level access to Linux network devices

SYNOPSIS

```
#include <sys/ioctl.h>
#include <net/if.h>
```

DESCRIPTION

This man page describes the sockets interface which is used to configure network devices.

Linux supports some standard ioctls to configure network devices. They can be used on any socket's file descriptor regardless of the family or type. Most of them pass an *ifreq* structure:

```
struct ifreq {
   char ifr_name[IFNAMSIZ]; /* Interface name */
   union {
       struct sockaddr ifr_addr;
        struct sockaddr ifr_dstaddr;
        struct sockaddr ifr_broadaddr;
        struct sockaddr ifr_netmask;
        struct sockaddr ifr_hwaddr;
                       ifr_flags;
        short
                       ifr_ifindex;
        int
        int
                       ifr_metric;
        int
                       ifr_mtu;
        struct ifmap ifr_map;
                        ifr_slave[IFNAMSIZ];
        char
                       ifr_newname[IFNAMSIZ];
        char
                       *ifr data;
        char
   };
};
```

Normally, the user specifies which device to affect by setting *ifr_name* to the name of the interface. All other members of the structure may share memory.

Ioctls

If an ioctl is marked as privileged, then using it requires an effective user ID of 0 or the CAP_NET_AD-MIN capability. If this is not the case, EPERM will be returned.

SIOCGIFNAME

Given the *ifr_ifindex*, return the name of the interface in *ifr_name*. This is the only ioctl which returns its result in *ifr_name*.

SIOCGIFINDEX

Retrieve the interface index of the interface into *ifr ifindex*.

SIOCGIFFLAGS, SIOCSIFFLAGS

Get or set the active flag word of the device. *ifr_flags* contains a bit mask of the following values:

```
Device flags
IFF UP
                      Interface is running.
IFF_BROADCAST
                       Valid broadcast address set.
IFF DEBUG
                       Internal debugging flag.
IFF LOOPBACK
                       Interface is a loopback interface.
IFF POINTOPOINT
                      Interface is a point-to-point link.
IFF RUNNING
                       Resources allocated.
IFF_NOARP
                      No arp protocol, L2 destination address not
IFF_PROMISC
                       Interface is in promiscuous mode.
```

IFF_NOTRAILERS	Avoid use of trailers.
IFF_ALLMULTI	Receive all multicast packets.
IFF_MASTER	Master of a load balancing bundle.
IFF_SLAVE	Slave of a load balancing bundle.
IFF_MULTICAST	Supports multicast
IFF_PORTSEL	Is able to select media type via ifmap.
IFF_AUTOMEDIA	Auto media selection active.
IFF_DYNAMIC	The addresses are lost when the interface
	goes down.
IFF_LOWER_UP	Driver signals L1 up (since Linux 2.6.17)
IFF_DORMANT	Driver signals dormant (since Linux 2.6.17)
IFF_ECHO	Echo sent packets (since Linux 2.6.25)

Setting the active flag word is a privileged operation, but any process may read it.

SIOCGIFPFLAGS, SIOCSIFPFLAGS

Get or set extended (private) flags for the device. *ifr_flags* contains a bit mask of the following values:

	Private flags
IFF_802_1Q_VLAN	Interface is 802.1Q VLAN device.
IFF_EBRIDGE	Interface is Ethernet bridging device.
IFF_SLAVE_INACTIVE	Interface is inactive bonding slave.
IFF_MASTER_8023AD	Interface is 802.3ad bonding master.
IFF_MASTER_ALB	Interface is balanced-alb bonding master.
IFF_BONDING	Interface is a bonding master or slave.
IFF_SLAVE_NEEDARP	Interface needs ARPs for validation.
IFF_ISATAP	Interface is RFC4214 ISATAP interface.

Setting the extended (private) interface flags is a privileged operation.

SIOCGIFADDR, SIOCSIFADDR

Get or set the address of the device using *ifr_addr*. Setting the interface address is a privileged operation. For compatibility, only **AF_INET** addresses are accepted or returned.

SIOCGIFDSTADDR, SIOCSIFDSTADDR

Get or set the destination address of a point-to-point device using *ifr_dstaddr*. For compatibility, only **AF_INET** addresses are accepted or returned. Setting the destination address is a privileged operation.

SIOCGIFBRDADDR, SIOCSIFBRDADDR

Get or set the broadcast address for a device using *ifr_brdaddr*. For compatibility, only **AF_INET** addresses are accepted or returned. Setting the broadcast address is a privileged operation.

SIOCGIFNETMASK, SIOCSIFNETMASK

Get or set the network mask for a device using *ifr_netmask*. For compatibility, only **AF_INET** addresses are accepted or returned. Setting the network mask is a privileged operation.

SIOCGIFMETRIC, SIOCSIFMETRIC

Get or set the metric of the device using *ifr_metric*. This is currently not implemented; it sets *ifr_metric* to 0 if you attempt to read it and returns **EOPNOTSUPP** if you attempt to set it.

SIOCGIFMTU, SIOCSIFMTU

Get or set the MTU (Maximum Transfer Unit) of a device using *ifr_mtu*. Setting the MTU is a privileged operation. Setting the MTU to too small values may cause kernel crashes.

SIOCGIFHWADDR. SIOCSIFHWADDR

Get or set the hardware address of a device using *ifr_hwaddr*. The hardware address is specified in a struct *sockaddr*. *sa_family* contains the ARPHRD_* device type, *sa_data* the L2 hardware address starting from byte 0. Setting the hardware address is a privileged operation.

NETDEVICE(7)

SIOCSIFHWBROADCAST

Set the hardware broadcast address of a device from *ifr_hwaddr*. This is a privileged operation.

SIOCGIFMAP, SIOCSIFMAP

Get or set the interface's hardware parameters using *ifr_map*. Setting the parameters is a privileged operation.

```
struct ifmap {
   unsigned long mem_start;
   unsigned long mem_end;
   unsigned short base_addr;
   unsigned char irq;
   unsigned char dma;
   unsigned char port;
};
```

The interpretation of the ifmap structure depends on the device driver and the architecture.

SIOCADDMULTI, SIOCDELMULTI

Add an address to or delete an address from the device's link layer multicast filters using *ifr_hwaddr*. These are privileged operations. See also **packet**(7) for an alternative.

SIOCGIFTXQLEN, SIOCSIFTXQLEN

Get or set the transmit queue length of a device using *ifr_qlen*. Setting the transmit queue length is a privileged operation.

SIOCSIFNAME

Changes the name of the interface specified in *ifr_name* to *ifr_newname*. This is a privileged operation. It is allowed only when the interface is not up.

SIOCGIFCONF

Return a list of interface (network layer) addresses. This currently means only addresses of the **AF_INET** (IPv4) family for compatibility. Unlike the others, this ioctl passes an *ifconf* structure:

If *ifc_req* is NULL, **SIOCGIFCONF** returns the necessary buffer size in bytes for receiving all available addresses in *ifc_len*. Otherwise, *ifc_req* contains a pointer to an array of *ifreq* structures to be filled with all currently active L3 interface addresses. *ifc_len* contains the size of the array in bytes. Within each *ifreq* structure, *ifr_name* will receive the interface name, and *ifr_addr* the address. The actual number of bytes transferred is returned in *ifc_len*.

If the size specified by *ifc_len* is insufficient to store all the addresses, the kernel will skip the exceeding ones and return success. There is no reliable way of detecting this condition once it has occurred. It is therefore recommended to either determine the necessary buffer size beforehand by calling **SIOCGIFCONF** with *ifc_req* set to NULL, or to retry the call with a bigger buffer whenever *ifc_len* upon return differs by less than *sizeof(struct ifreq)* from its original value.

If an error occurs accessing the *ifconf* or *ifreq* structures, **EFAULT** will be returned.

Most protocols support their own ioctls to configure protocol-specific interface options. See the protocol man pages for a description. For configuring IP addresses, see **ip**(7).

In addition, some devices support private ioctls. These are not described here.

Linux 2019-11-19 3

NOTES

Strictly speaking, **SIOCGIFCONF** and the other ioctls that accept or return only **AF_INET** socket addresses, are IP-specific and belong in **ip**(7).

The names of interfaces with no addresses or that don't have the **IFF_RUNNING** flag set can be found via /proc/net/dev.

Local IPv6 IP addresses can be found via /proc/net or via **rtnetlink**(7).

BUGS

glibc 2.1 is missing the *ifr_newname* macro in *<net/if.h>*. Add the following to your program as a workaround:

SEE ALSO

```
proc(5), capabilities(7), ip(7), rtnetlink(7)
```

COLOPHON

This page is part of release 5.05 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux 2019-11-19 4