

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'dlsym.3'

\$ man dlsym.3

DLSYM(3)

Linux Programmer's Manual

DLSYM(3)

NAME

dlsym, dlvsym - obtain address of a symbol in a shared object or executable

SYNOPSIS

#include <dlfcn.h>

void *dlsym(void *handle, const char *symbol);

#define _GNU_SOURCE

#include <dlfcn.h>

void *dlvsym(void *handle, char *symbol, char *version);

Link with -ldl.

DESCRIPTION

The function dlsym() takes a "handle" of a dynamic loaded shared object returned by dlopen(3) along with a null-terminated symbol name, and returns the address where that symbol is loaded into memory. If the symbol is not found, in the specified object or any of the shared objects that were automatically loaded by dlopen(3) when that object was loaded, dlsym() returns NULL. (The search performed by dlsym() is breadth first through the dependency tree of these shared objects.)

In unusual cases (see NOTES) the value of the symbol could actually be NULL. Therefore, a NULL return from dlsym() need not indicate an error. The correct way to distinguish an error from a symbol whose value is NULL is to call dlerror(3) to clear any old error con? ditions, then call dlsym(), and then call dlerror(3) again, saving its return value into a variable, and check whether this saved value is not NULL.

There are two special pseudo-handles that may be specified in handle:

RTLD DEFAULT

Find the first occurrence of the desired symbol using the default shared object search order. The search will include global symbols in the executable and its de? pendencies, as well as symbols in shared objects that were dynamically loaded with the RTLD_GLOBAL flag.

RTLD NEXT

Find the next occurrence of the desired symbol in the search order after the cur? rent object. This allows one to provide a wrapper around a function in another shared object, so that, for example, the definition of a function in a preloaded shared object (see LD_PRELOAD in Id.so(8)) can find and invoke the "real" function provided in another shared object (or for that matter, the "next" definition of the function in cases where there are multiple layers of preloading).

The _GNU_SOURCE feature test macro must be defined in order to obtain the definitions of RTLD_DEFAULT and RTLD_NEXT from <dlfcn.h>.

The function dlvsym() does the same as dlsym() but takes a version string as an additional argument.

RETURN VALUE

On success, these functions return the address associated with symbol. On failure, they return NULL; the cause of the error can be diagnosed using dlerror(3).

VERSIONS

dlsym() is present in glibc 2.0 and later. dlvsym() first appeared in glibc 2.1.

ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

?Interface ? Attribute ? Value ?

?dlsym(), dlvsym() ? Thread safety ? MT-Safe ?

CONFORMING TO

POSIX.1-2001 describes dlsym(). The dlvsym() function is a GNU extension.

NOTES

There are several scenarios when the address of a global symbol is NULL. For example, a symbol can be placed at zero address by the linker, via a linker script or with --defsym

command-line option. Undefined weak symbols also have NULL value. Finally, the symbol value may be the result of a GNU indirect function (IFUNC) resolver function that returns NULL as the resolved value. In the latter case, dlsym() also returns NULL without error. However, in the former two cases, the behavior of GNU dynamic linker is inconsistent: re? location processing succeeds and the symbol can be observed to have NULL value, but dl? sym() fails and dlerror() indicates a lookup error.

History

The dlsym() function is part of the dlopen API, derived from SunOS. That system does not have dlvsym().

EXAMPLES

See dlopen(3).

SEE ALSO

dl_iterate_phdr(3), dladdr(3), dlerror(3), dlinfo(3), dlopen(3), ld.so(8)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux 2020-06-09 DLSYM(3)