

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'git-init.1'

\$ man git-init.1

GIT-INIT(1)

Git Manual

GIT-INIT(1)

NAME

git-init - Create an empty Git repository or reinitialize an existing one

SYNOPSIS

git init [-q | --quiet] [--bare] [--template=<template_directory>]

[--separate-git-dir < git dir >] [--object-format=< format>]

[-b <branch-name> | --initial-branch=<branch-name>]

[--shared[=<permissions>]] [directory]

DESCRIPTION

This command creates an empty Git repository - basically a .git directory with subdirectories for objects, refs/heads, refs/tags, and template files. An initial branch without any commits will be created (see the --initial-branch option below for its name). If the \$GIT_DIR environment variable is set then it specifies a path to use instead of ./.git for the base of the repository.

If the object storage directory is specified via the \$GIT_OBJECT_DIRECTORY environment variable then the sha1 directories are created underneath - otherwise the default \$GIT_DIR/objects directory is used.

Running git init in an existing repository is safe. It will not overwrite things that are already there. The primary reason for rerunning git init is to pick up newly added templates (or to move the repository to another place if --separate-git-dir is given).

OPTIONS

-q, --quiet

--bare

Create a bare repository. If GIT_DIR environment is not set, it is set to the current working directory.

--object-format=<format>

Specify the given object format (hash algorithm) for the repository. The valid values are sha1 and (if enabled) sha256. sha1 is the default.

THIS OPTION IS EXPERIMENTAL! SHA-256 support is experimental and still in an early stage. A SHA-256 repository will in general not be able to share work with "regular" SHA-1 repositories. It should be assumed that, e.g., Git internal file formats in relation to SHA-256 repositories may change in backwards-incompatible ways. Only use --object-format=sha256 for testing purposes.

--template=<template_directory>

Specify the directory from which templates will be used. (See the "TEMPLATE DIRECTORY" section below.)

--separate-git-dir=<git dir>

Instead of initializing the repository as a directory to either \$GIT_DIR or ./.git/, create a text file there containing the path to the actual repository. This file acts as filesystem-agnostic Git symbolic link to the repository.

If this is reinitialization, the repository will be moved to the specified path.

-b
branch-name>, --initial-branch=
branch-name>

Use the specified name for the initial branch in the newly created repository. If not specified, fall back to the default name (currently master, but this is subject to change in the future; the name can be customized via the init.defaultBranch configuration variable).

--shared[=(false|true|umask|group|all|world|everybody|0xxx)]

Specify that the Git repository is to be shared amongst several users. This allows users belonging to the same group to push into that repository. When specified, the config variable "core.sharedRepository" is set so that files and directories under \$GIT_DIR are created with the requested permissions. When not specified, Git will use permissions reported by umask(2).

The option can have the following values, defaulting to group if no value is given: umask (or false)

group (or true)

Make the repository group-writable, (and g+sx, since the git group may be not the primary group of all users). This is used to loosen the permissions of an otherwise safe umask(2) value. Note that the umask still applies to the other permission bits (e.g. if umask is 0022, using group will not remove read privileges from other (non-group) users). See 0xxx for how to exactly specify the repository permissions.

all (or world or everybody)

Same as group, but make the repository readable by all users.

0xxx

0xxx is an octal number and each file will have mode 0xxx. 0xxx will override users' umask(2) value (and not only loosen permissions as group and all does). 0640 will create a repository which is group-readable, but not group-writable or accessible to others. 0660 will create a repo that is readable and writable to the current user and group, but inaccessible to others.

By default, the configuration flag receive.denyNonFastForwards is enabled in shared repositories, so that you cannot force a non fast-forwarding push into it.

If you provide a directory, the command is run inside it. If this directory does not exist, it will be created.

TEMPLATE DIRECTORY

Files and directories in the template directory whose name do not start with a dot will be copied to the \$GIT_DIR after it is created.

The template directory will be one of the following (in order):

- ? the argument given with the --template option;
- ? the contents of the \$GIT_TEMPLATE_DIR environment variable;
- ? the init.templateDir configuration variable; or
- ? the default template directory: /usr/share/git-core/templates.

The default template directory includes some directory structure, suggested "exclude patterns" (see gitignore(5)), and sample hook files.

The sample hooks are all disabled by default. To enable one of the sample hooks rename it by removing its .sample suffix.

See githooks(5) for more general info on hook execution.

EXAMPLES Page 3/4

Start a new Git repository for an existing code base

\$ cd /path/to/my/codebase

\$ git init (1)

\$ git add . (2)

\$ git commit (3)

- 1. Create a /path/to/my/codebase/.git directory.
- 2. Add all existing files to the index.
- 3. Record the pristine state as the first commit in the history.

GIT

Part of the git(1) suite

Git 2.34.1 07/07/2023 GIT-INIT(1)