

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'sane-gphoto2.5'

\$ man sane-gphoto2.5

sane-gphoto2(5)

SANE Scanner Access Now Easy

sane-gphoto2(5)

NAME

sane-gphoto2 - SANE backend for gphoto2 supported cameras

DESCRIPTION

The sane-gphoto2 library implements a SANE (Scanner Access Now Easy) backend that provides access to the digital cameras supported by gphoto2. This backend has only been tested with a handful of cameras so far. Patches to support other models are welcome.

Because of the limited testing of this backend, it is commented out in /etc/sane.d/dll.conf by default. Either the comment character must be removed or the backend must be called explicitly. E.g. scanimage -d gphoto2 or xscanimage gphoto2.

DEVICE NAMES

The current version of the backend only allows one camera to be connected. The device name is always "0".

CONFIGURATION

The contents of the gphoto2.conf specify the characteristics of the camera to be used.

Resolutions (high resolution, low resolution, and thumbnail size) are required since they are needed by the sane frontends, but can't be obtained through the gphoto2 interface.

Valid ports and cameras can be obtained by gphoto2 --list-cameras and gphoto2 --list-ports

The dumpinguiry line causes some information about the camera to be printed.

Empty lines and lines starting with a hash mark (#) are ignored. A sample configuration file is shown below:

The topfolder line specifies the "fixed" part of the file path. For example, on the Kodak

DC-240, files are stored in the directory /DCIM/100DC240. The /DCIM portion is constant, but 100DC240 will change and must be read from the camera. In this case, the line would read "topfolder=/DCIM"

Some cameras don't implement a file structure and store all pictures in the / directory.

This is indicated by setting "subdirs=0" with "topfolder=/"

port=usb:

camera=Kodak DC240

this is a comment

high resolution=1280x960

low resolution=640x480

thumb_resolution=160x120

dumpinguiry

FILES

/etc/sane.d/gphoto2.conf

The backend configuration file (see also description of SANE_CONFIG_DIR below).

/usr/lib/x86_64-linux-gnu/sane/libsane-gphoto2.a

The static library implementing this backend.

/usr/lib/x86_64-linux-gnu/sane/libsane-gphoto2.so

The shared library implementing this backend (present on systems that support dy? namic loading).

ENVIRONMENT

SANE_CONFIG_DIR

This environment variable specifies the list of directories that may contain the configuration file. On *NIX systems, the directories are separated by a colon (`:'), under OS/2, they are separated by a semi-colon (`;'). If this variable is not set, the configuration file is searched in two default directories: first, the current working directory (.) and then in /etc/sane.d. If the value of the envi? ronment variable ends with the directory separator character, then the default di? rectories are searched after the explicitly specified directories. For example, setting SANE_CONFIG_DIR to "/tmp/config:" would result in directories tmp/config, ., and /etc/sane.d being searched (in this order).

SANE_DEBUG_GPHOTO2

able controls the debug level for this backend. A value of 128 requests maximally copious debug output; smaller levels reduce verbosity.

GP_DEBUG

Set to 1, 2, or 3, to enable various levels of debugging within the gphoto2 li? braries.

SEE ALSO

sane(7), scanimage(1), xscanimage(1), libgphoto2(3)

AUTHOR

Peter S. Fales

The manpage was largely copied from the sane-dc210(5) manpage.

BUGS

Many, no doubt.

More general comments, suggestions, and inquiries about frontends or SANE should go to the SANE Developers mailing list (see http://www.sane-project.org/mailing-lists.html for de? tails). You must be subscribed to the list, otherwise your mail won't be sent to the sub? scribers.

11 Jul 2008

sane-gphoto2(5)