



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'wcstombs.3'

\$ man wcstombs.3

WCSTOMBS(3) Linux Programmer's Manual WCSTOMBS(3)

NAME

wcstombs - convert a wide-character string to a multibyte string

SYNOPSIS

```
#include <stdlib.h>

size_t wcstombs(char *dest, const wchar_t *src, size_t n);
```

DESCRIPTION

If `dest` is not NULL, the `wcstombs()` function converts the wide-character string `src` to a multibyte string starting at `dest`. At most `n` bytes are written to `dest`. The sequence of characters placed in `dest` begins in the initial shift state. The conversion can stop for three reasons:

1. A wide character has been encountered that can not be represented as a multibyte sequence (according to the current locale). In this case, `(size_t) -1` is returned.
2. The `length` limit forces a stop. In this case, the number of bytes written to `dest` is returned, but the shift state at this point is lost.
3. The wide-character string has been completely converted, including the terminating null wide character (`L'\0'`). In this case, the conversion ends in the initial shift state. The number of bytes written to `dest`, excluding the terminating null byte (`\0`), is returned.

The programmer must ensure that there is room for at least `n` bytes at `dest`.

If `dest` is NULL, `n` is ignored, and the conversion proceeds as above, except that the converted bytes are not written out to memory, and no length limit exists.

In order to avoid the case 2 above, the programmer should make sure `n` is greater than or

equal to `wcstombs(NULL,src,0)+1`.

RETURN VALUE

The `wcstombs()` function returns the number of bytes that make up the converted part of a multibyte sequence, not including the terminating null byte. If a wide character was encountered which could not be converted, `(size_t) -1` is returned.

ATTRIBUTES

For an explanation of the terms used in this section, see [attributes\(7\)](#).

????????????????????????????????????????????????????????

?Interface ? Attribute ? Value ?

????????????????????????????????????????????????????????

?`wcstombs()` ? Thread safety ? MT-Safe ?

????????????????????????????????????????????????????????

CONFORMING TO

POSIX.1-2001, POSIX.1-2008, C99.

NOTES

The behavior of `wcstombs()` depends on the `LC_CTYPE` category of the current locale.

The function `wcsrtombs(3)` provides a better interface to the same functionality.

SEE ALSO

[mblen\(3\)](#), [mbstowcs\(3\)](#), [mbtowc\(3\)](#), [wcsrtombs\(3\)](#), [wctomb\(3\)](#)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.