

Full credit is given to the above companies including the OS that this PDF file was generated!

# Red Hat Enterprise Linux Release 9.2 Manual Pages on 'mpathpersist.8' command

## \$ man mpathpersist.8

MPATHPERSIST(8)

System Manager's Manual

MPATHPERSIST(8)

NAME

mpathpersist - Manages SCSI persistent reservations on dm multipath de? vices.

**SYNOPSIS** 

mpathpersist [OPTIONS] device

#### **DESCRIPTION**

This utility is used to manage SCSI persistent reservations on Device Mapper Multipath devices. To be able to use this functionality, the reservation\_key attribute must be defined in the /etc/multipath.conf file. Otherwise the multipathd daemon will not check for persistent reservation for newly discovered paths or reinstated paths. mpathpersist supports the same command-line options as the sg\_persist utility. Consult the sg\_persist (8) manual page for an in-depth dis? cussion of the various options.

#### **OPTIONS**

-verbose|-v level

Verbosity:

- Critical messages.
- Error messages.
- 2 Warning messages.
- 3 Informational messages.
- 4 Informational messages with trace enabled.

```
--device=DEVICE|-d DEVICE
    Query or change DEVICE.
--batch-file=DEVICE|-f FILE
    Read commands from FILE. See section "BATCH FILES" below. This
    option can be given at most once.
--help|-h
    Output this usage message.
--hex|-H
    Output response in hex.
--in|-i
    Request PR In command.
--out|-o
    Request PR Out command.
--param-alltgpt|-Y
    PR Out parameter 'ALL_TG_PT'.
--param-aptpl|-Z
    PR Out parameter 'APTPL'.
--read-keys|-k
    PR In: Read Keys.
--param-rk=RK|-K RK
    PR Out parameter reservation key (RK is in hex, up to 8 bytes).
--param-sark=SARK|-S SARK
    PR Out parameter service action reservation key (SARK is in
    hex).
--preempt|-P
    PR Out: Preempt.
--clear|-C
    PR Out: Clear registrations.
--preempt-abort|-A
    PR Out: Preempt and Abort.
--prout-type=TYPE|-T TYPE
    PR Out command type.
```

--read-full-status|-s

Page 2/5

```
PR In: Read Full Status.
    --read-keys|-k
        PR In: Read Keys.
    --read-reservation|-r
        PR In: Read Reservation.
    --register|-G
        PR Out: Register.
    --register-ignore|-I
        PR Out: Register and Ignore.
    --release|-L
        PR Out: Release.
    --report-capabilities|-c
        PR In: Report Capabilities.
    --reserve|-R
        PR Out: Reserve.
    --transport-id=TIDS|-X TIDS
        TransportIDs can be mentioned in several forms.
    --alloc-length=LEN|-I LEN
        PR In: maximum allocation length. LEN is a decimal number be?
        tween 0 and 8192.
EXAMPLE
    Register the key "123abc" for the /dev/mapper/mpath9 device:
        mpathpersist --out --register --param-sark=123abc /dev/map?
        per/mpath9
    Read registered reservation keys for the /dev/mapper/mpath9 device:
        mpathpersist -i -k /dev/mapper/mpath9
    Create a reservation for the /dev/mapper/mpath9 device with the given
    reservation key:
        mpathpersist --out --reserve --param-rk=123abc --prout-type=8 -d
        /dev/mapper/mpath9
    Read the reservation status of the /dev/mapper/mpath9 device:
        mpathpersist -i -s -d /dev/mapper/mpath9
```

Release the previously created reservation (note that the prout-type

needs to be the same as above):

mpathpersist --out --release --param-rk=123abc --prout-type=8 -d /dev/mapper/mpath9

Remove the current key registered for this host (i.e. reset it to 0):

mpathpersist --out --register-ignore -K 123abc -S 0 /dev/map?

per/mpath9

Remove current reservation, and unregister all registered keys from all I\_T nexuses:

mpathpersist -oCK 123abc /dev/mapper/mpath9

#### **BATCH FILES**

The option --batch-file (-f) sets an input file to be processed by mpathpersist. Grouping commands in batch files can provide a speed im? provement in particular on large installments, because mpathpersist needs to scan existing paths and maps only once during startup.

The input file is a text file that is parsed line by line. Every line of the file is interpreted as a command line (i.e. list of options and parameters) for mpathpersist. Options and parameters are separated by one or more whitespace characters (space or TAB). Lines can, but do not have to, begin with the word "mpathpersist". The "#" character, either at the beginning of the line or following some whitespace, de? notes the start of a comment that lasts until the end of the line.

Empty lines are allowed. Continuation of mpathpersist commands over multiple lines is not supported.

All options listed in this man page, except -f and -v, are allowed in batch files. Both short and long option formats may be used. Using the -f option inside the batch file is an error. The -v option is ignored in batch files.

The multipath map on which to act must be specified on every input line, e.g. using the -d option. Commands acting on different multipath maps may be combined in a batch file, and multiple commands may act on the same multipath map. Commands are executed one by one, so that com? mands further down in the file see status changes caused by previous commands. If mpathpersist encounters an error while processing a line

in the batch file, batch file processing is not aborted; subsequent commands are executed nonetheless. The exit status of mpathpersist is the status of the first failed command, or 0 if all commands succeeded. If other options and parameters are used along with -f on the mpathper? sist command line, the command line will be executed first, followed by the commands from the the batch file.

Below is an example of a valid batch input file.

- # This is an mpathpersist input file.
- # Short and long forms of the same command
- -i -k /dev/dm-1 # short form, this comment is ignored
- mpathpersist --in --read-keys --device=/dev/dm-1
- # Mixing of long and short options, variable white space
- --out --register -S abcde /dev/dm-1
- # Mixing of commands for different maps
- -ir /dev/dm-0
- -ir /dev/dm-1

mpathpersist --out --param-rk abcde --reserve --prout-type 5 /dev/dm-1

- # This should now show a reservation
- -ir /dev/dm-1
- -oCK abcde /dev/dm-1
- --in --read-reservation /dev/dm-1

### SEE ALSO

multipath(8), multipathd(8), sg\_persist(8).

#### **AUTHORS**

multipath-tools was developed by Christophe Varoqui <christophe.varo? qui@opensvc.com> and others.

Linux 2019-05-27 MPATHPERSIST(8)