



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'getfsfile.3'***

#### ***\$ man getfsfile.3***

GETFSENT(3)           Linux Programmer's Manual           GETFSENT(3)

#### NAME

getfsent, getfsspec, getfsfile, setfsent, endfsent - handle fstab en?

tries

#### SYNOPSIS

```
#include <fstab.h>

void endfsent(void);

struct fstab *getfsent(void);

struct fstab *getfsfile(const char *mount_point);

struct fstab *getfsspec(const char *special_file);

int setfsent(void);
```

#### DESCRIPTION

These functions read from the file /etc/fstab. The struct fstab is de?

fined by:

```
struct fstab {
    char    *fs_spec;    /* block device name */
    char    *fs_file;    /* mount point */
    char    *fs_vfstype; /* file-system type */
```

```

char    *fs_mntops; /* mount options */
const char *fs_type; /* rw/rq/ro/sw/xx option */
int     fs_freq; /* dump frequency, in days */
int     fs_passno; /* pass number on parallel dump */
};

```

Here the field `fs_type` contains (on a \*BSD system) one of the five strings "rw", "rq", "ro", "sw", "xx" (read-write, read-write with quota, read-only, swap, ignore).

The function `setfsent()` opens the file when required and positions it at the first line.

The function `getfsent()` parses the next line from the file. (After opening it when required.)

The function `endfsent()` closes the file when required.

The function `getfsspec()` searches the file from the start and returns the first entry found for which the `fs_spec` field matches the `special_file` argument.

The function `getfsfile()` searches the file from the start and returns the first entry found for which the `fs_file` field matches the `mount_point` argument.

## RETURN VALUE

Upon success, the functions `getfsent()`, `getfsfile()`, and `getfsspec()` return a pointer to a struct `fstab`, while `setfsent()` returns 1. Upon failure or end-of-file, these functions return NULL and 0, respectively.

## ATTRIBUTES

For an explanation of the terms used in this section, see [attributes\(7\)](#).

??

?Interface ? Attribute ? Value ?

??

?endfsent(), ? Thread safety ? MT-Unsafe race:fsent ?

?setfsent() ? ? ?

??

?getfsent(), ? Thread safety ? MT-Unsafe race:fisent locale ?  
?getfsspec(), ? ? ?  
?getfsfile() ? ? ?  
??

### CONFORMING TO

These functions are not in POSIX.1. Several operating systems have them, for example, \*BSD, SunOS, Digital UNIX, AIX (which also has a getfstype()). HP-UX has functions of the same names, that however use a struct checklist instead of a struct fstab, and calls these functions obsolete, superseded by getmntent(3).

### NOTES

These functions are not thread-safe.

Since Linux allows mounting a block special device in several places, and since several devices can have the same mount point, where the last device with a given mount point is the interesting one, while getfsfile() and getfsspec() only return the first occurrence, these two functions are not suitable for use under Linux.

### SEE ALSO

getmntent(3), fstab(5)

### COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

GNU 2017-09-15 GETFSENT(3)