

Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'locale.conf.5'

\$ man locale.conf.5

LOCALE.CONF(5)

locale.conf

LOCALE.CONF(5)

NAME

locale.conf - Configuration file for locale settings

SYNOPSIS

/etc/locale.conf

DESCRIPTION

The /etc/locale.conf file configures system-wide locale settings. It is

read at early boot by systemd(1).

The format of locale.conf is a newline-separated list of

environment-like shell-compatible variable assignments, ignoring

comments and empty lines. It is possible to source the configuration

from shell scripts, however, beyond mere variable assignments, no shell

features are supported, allowing applications to read the file without

implementing a shell compatible execution engine. See os-release(5) for

a detailed description of the format.

Note that the kernel command line options locale.LANG=,

locale.LANGUAGE=, locale.LC_CTYPE=, locale.LC_NUMERIC=,

locale.LC_TIME=, locale.LC_COLLATE=, locale.LC_MONETARY=,

locale.LC_MESSAGES=, locale.LC_PAPER=, locale.LC_NAME=,

locale.LC_ADDRESS=, locale.LC_TELEPHONE=, locale.LC_MEASUREMENT=,

locale.LC_IDENTIFICATION= may be used to override the locale settings at boot.

The locale settings configured in /etc/locale.conf are system-wide and are inherited by every service or user, unless overridden or unset by individual programs or users.

Depending on the operating system, other configuration files might be

checked for locale configuration as well, however only as fallback.

/etc/locale.conf can be updated using systemd-localed.service(8).

localectl(1) may be used to alter the settings in this file during

runtime from the command line. Use systemd-firstboot(1) to customize

them on mounted (but not booted) system images.

OPTIONS

The following locale settings may be set using /etc/locale.conf: LANG=,

LANGUAGE=, LC_CTYPE=, LC_NUMERIC=, LC_TIME=, LC_COLLATE=, LC_MONETARY=,

LC_MESSAGES=, LC_PAPER=, LC_NAME=, LC_ADDRESS=, LC_TELEPHONE=,

LC_MEASUREMENT=, LC_IDENTIFICATION=. Note that LC_ALL may not be

configured in this file. For details about the meaning and semantics of

these settings, refer to locale(7).

EXAMPLE

Example 1. German locale with English messages

/etc/locale.conf:

Custom settings

LANG=de_DE.UTF-8

LC_MESSAGES=en_US.UTF-8

SEE ALSO

systemd(1), locale(7), localectl(1), systemd-localed.service(8),

systemd-firstboot(1)

systemd 252

LOCALE.CONF(5)