



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'pam_securetty.8'

\$ man pam_securetty.8

PAM_SECURETTY(8) Linux-PAM Manual PAM_SECURETTY(8)

NAME

pam_securetty - Limit root login to special devices

SYNOPSIS

pam_securetty.so [debug]

DESCRIPTION

pam_securetty is a PAM module that allows root logins only if the user is logging in on a "secure" tty, as defined by the listing in the securetty file. pam_securetty checks at first, if /etc/securetty exists. If not and it was built with vendordir support, it will use <vendordir>/securetty. pam_securetty also checks that the securetty files are plain files and not world writable. It will also allow root logins on the tty specified with console= switch on the kernel command line and on ttys from the /sys/class/tty/console/active.

This module has no effect on non-root users and requires that the application fills in the PAM_TTY item correctly.

For canonical usage, should be listed as a required authentication method before any sufficient authentication methods.

OPTIONS

debug

Print debug information.

noconsole

Do not automatically allow root logins on the kernel console device, as specified on the kernel command line or by the sys file, if it is not also specified in the securetty file.

MODULE TYPES PROVIDED

Only the auth module type is provided.

RETURN VALUES

PAM_SUCCESS

The user is allowed to continue authentication. Either the user is not root, or the root user is trying to log in on an acceptable device.

PAM_AUTH_ERR

Authentication is rejected. Either root is attempting to log in via an unacceptable device, or the securetty file is world writable or not a normal file.

PAM_BUF_ERR

Memory buffer error.

PAM_CONV_ERR

The conversation method supplied by the application failed to obtain the username.

PAM_INCOMPLETE

The conversation method supplied by the application returned PAM_CONV_AGAIN.

PAM_SERVICE_ERR

An error occurred while the module was determining the user's name or tty, or the module could not open the securetty file.

PAM_USER_UNKNOWN

The module could not find the user name in the /etc/passwd file to verify whether the user had a UID of 0. Therefore, the results of running this module are ignored.

EXAMPLES

```
auth required pam_securetty.so
```

```
auth required pam_unix.so
```

SEE ALSO

securetty(5), pam.conf(5), pam.d(5), pam(8)

AUTHOR

pam_securetty was written by Elliot Lee <sopwith@cuc.edu>.

Linux-PAM Manual

11/25/2020

PAM_SECURETTY(8)