

Full credit is given to the above companies including the OS that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'secure\_getenv.3'

## \$ man secure\_getenv.3

GETENV(3)

Linux Programmer's Manual

GETENV(3)

NAME

getenv, secure\_getenv - get an environment variable

#### **SYNOPSIS**

#include <stdlib.h>

char \*getenv(const char \*name);

char \*secure\_getenv(const char \*name);

Feature Test Macro Requirements for glibc (see feature\_test\_macros(7)):

secure\_getenv(): \_GNU\_SOURCE

#### **DESCRIPTION**

The getenv() function searches the environment list to find the envi? ronment variable name, and returns a pointer to the corresponding value string.

The GNU-specific secure\_getenv() function is just like getenv() except that it returns NULL in cases where "secure execution" is required.

Secure execution is required if one of the following conditions was true when the program run by the calling process was loaded:

<sup>\*</sup> the process's effective user ID did not match its real user ID or

the process's effective group ID did not match its real group ID (typically this is the result of executing a set-user-ID or set-group-ID program);

- \* the effective capability bit was set on the executable file; or
- \* the process has a nonempty permitted capability set.

Secure execution may also be required if triggered by some Linux secu? rity modules.

The secure\_getenv() function is intended for use in general-purpose li? braries to avoid vulnerabilities that could occur if set-user-ID or set-group-ID programs accidentally trusted the environment.

#### **RETURN VALUE**

The getenv() function returns a pointer to the value in the environ? ment, or NULL if there is no match.

#### **VERSIONS**

secure\_getenv() first appeared in glibc 2.17.

#### **ATTRIBUTES**

For an explanation of the terms used in this section, see at? tributes(7).

?Interface ? Attribute ? Value ?

?getenv(), secure\_getenv() ? Thread safety ? MT-Safe env ?

#### **CONFORMING TO**

getenv(): POSIX.1-2001, POSIX.1-2008, C89, C99, SVr4, 4.3BSD. secure getenv() is a GNU extension.

#### **NOTES**

The strings in the environment list are of the form name=value.

As typically implemented, getenv() returns a pointer to a string within the environment list. The caller must take care not to modify this string, since that would change the environment of the process.

The implementation of getenv() is not required to be reentrant. The string pointed to by the return value of getenv() may be statically al?

located, and can be modified by a subsequent call to getenv(), putenv(3), setenv(3), or unsetenv(3).

The "secure execution" mode of secure\_getenv() is controlled by the AT\_SECURE flag contained in the auxiliary vector passed from the kernel to user space.

## SEE ALSO

clearenv(3), getauxval(3), putenv(3), setenv(3), unsetenv(3), capabili? ties(7), environ(7)

## **COLOPHON**

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

GNU 2017-09-15 GETENV(3)