

# Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'getenv.3'

# \$ man getenv.3

GETENV(3)

/(3) Linux Programmer's Manual

GETENV(3)

# NAME

getenv, secure\_getenv - get an environment variable

# SYNOPSIS

#include <stdlib.h>

char \*getenv(const char \*name);

char \*secure\_getenv(const char \*name);

Feature Test Macro Requirements for glibc (see feature\_test\_macros(7)):

secure\_getenv(): \_GNU\_SOURCE

# DESCRIPTION

The getenv() function searches the environment list to find the environment variable name,

and returns a pointer to the corresponding value string.

The GNU-specific secure\_getenv() function is just like getenv() except that it returns NULL in cases where "secure execution" is required. Secure execution is required if one of the following conditions was true when the program run by the calling process was loaded:

- \* the process's effective user ID did not match its real user ID or the process's effec? tive group ID did not match its real group ID (typically this is the result of execut? ing a set-user-ID or set-group-ID program);
- \* the effective capability bit was set on the executable file; or
- \* the process has a nonempty permitted capability set.

Secure execution may also be required if triggered by some Linux security modules.

The secure\_getenv() function is intended for use in general-purpose libraries to avoid

vulnerabilities that could occur if set-user-ID or set-group-ID programs accidentally

trusted the environment.

#### **RETURN VALUE**

The getenv() function returns a pointer to the value in the environment, or NULL if there is no match.

#### VERSIONS

secure\_getenv() first appeared in glibc 2.17.

# ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

?Interface ? Attribute ? Value ?

?getenv(), secure\_getenv() ? Thread safety ? MT-Safe env ?

# CONFORMING TO

getenv(): POSIX.1-2001, POSIX.1-2008, C89, C99, SVr4, 4.3BSD.

secure\_getenv() is a GNU extension.

# NOTES

The strings in the environment list are of the form name=value.

As typically implemented, getenv() returns a pointer to a string within the environment

list. The caller must take care not to modify this string, since that would change the environment of the process.

The implementation of getenv() is not required to be reentrant. The string pointed to by the return value of getenv() may be statically allocated, and can be modified by a subse? guent call to getenv(), putenv(3), setenv(3), or unsetenv(3).

The "secure execution" mode of secure\_getenv() is controlled by the AT\_SECURE flag con? tained in the auxiliary vector passed from the kernel to user space.

# SEE ALSO

clearenv(3), getauxval(3), putenv(3), setenv(3), unsetenv(3), capabilities(7), environ(7)

# COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.