

Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'scriptreplay.1' command

\$ man scriptreplay.1

SCRIPTREPLAY(1)

SCRIPTREPLAY(1)

NAME

scriptreplay - play back typescripts, using timing information

SYNOPSIS

scriptreplay [options] [-t] timingfile [typescript [divisor]]

DESCRIPTION

This program replays a typescript, using timing information to ensure that output happens in the same rhythm as it originally appeared when

User Commands

the script was recorded.

The replay simply displays the information again; the programs that were run when the typescript was being recorded are not run again. Since the same information is simply being displayed, scriptreplay is only guaranteed to work properly if run on the same type of terminal the typescript was recorded on. Otherwise, any escape characters in the typescript may be interpreted differently by the terminal to which scriptreplay is sending its output.

The timing information is what script(1) outputs to file specified by --log-timing.

By default, the typescript to display is assumed to be named typescript, but other filenames may be specified, as the second parameter or with option --log-out. If the third parameter or --divisor is specified, it is used as a

speed-up multiplier. For example, a speed-up of 2 makes scriptreplay go

twice as fast, and a speed-up of 0.1 makes it go ten times slower than

the original session.

OPTIONS

-I, --log-in file

File containing script's terminal input.

-O, --log-out file

File containing script's terminal output.

-B, --log-io file

File containing script's terminal output and input.

-t, --timing file

File containing script's timing output. This option overrides

old-style arguments.

-T, --log-timing file

This is an alias for -t, maintained for compatibility with

script(1) command-line options.

-s, --typescript file

File containing script's terminal output. Deprecated alias to

--log-out. This option overrides old-style arguments.

-c, --cr-mode mode

Specifies how to use the CR (0x0D, carriage return) character from log files. The default mode is auto, in this case CR is replaced with line break for stdin log, because otherwise scriptreplay would overwrite the same line. The other modes are never and always.

-d, --divisor number

Speed up the replay displaying this number of times. The argument is a floating-point number. It?s called divisor because it divides the timings by this factor. This option overrides old-style arguments.

-m, --maxdelay number

Set the maximum delay between updates to number of seconds. The argument is a floating-point number. This can be used to avoid long pauses in the typescript replay.

Display details about the session recorded in the specified timing file and exit. The session has to be recorded using advanced format (see script(1)) option --logging-format for more details).

-x, --stream type

Forces scriptreplay to print only the specified stream. The supported stream types are in, out, signal, or info. This option is recommended for multi-stream logs (e.g., --log-io) in order to print only specified data.

-V, --version

Display version information and exit.

-h, --help

Display help text and exit.

EXAMPLES

% script --log-timing file.tm --log-out script.out

Script started, file is script.out

% ls

<etc, etc>

% exit

Script done, file is script.out

% scriptreplay --log-timing file.tm --log-out script.out

AUTHORS

The original scriptreplay program was written by Joey Hess

<joey@kitenet.net>. The program was re-written in C by James Youngman

<jay@gnu.org> and Karel Zak <kzak@redhat.com>

COPYRIGHT

Copyright ? 2008 James Youngman

Copyright ? 2008-2019 Karel Zak

This is free software; see the source for copying conditions. There is

NO warranty; not even for MERCHANTABILITY or FITNESS FOR A PARTICULAR

PURPOSE.

Released under the GNU General Public License version 2 or later.

SEE ALSO

REPORTING BUGS

For bug reports, use the issue tracker at

https://github.com/karelzak/util-linux/issues.

AVAILABILITY

The scriptreplay command is part of the util-linux package which can be

downloaded from Linux Kernel Archive

<https://www.kernel.org/pub/linux/utils/util-linux/>.

util-linux 2.37.4 2022-02-14 SCRIPTREPLAY(1)