



Red Hat Enterprise Linux Release 9.2 Manual Pages on 'setstate.3' command

\$ man setstate.3

RANDOM(3) Linux Programmer's Manual RANDOM(3)

NAME

random, srandom, initstate, setstate - random number generator

SYNOPSIS

```
#include <stdlib.h>

long random(void);

void srandom(unsigned seed);

char *initstate(unsigned seed, char *state, size_t n);

char *setstate(char *state);
```

Feature Test Macro Requirements for glibc (see feature_test_macros(7)):

```
random(), srandom(), initstate(), setstate():

_XOPEN_SOURCE >= 500

  /* Glibc since 2.19: */ _DEFAULT_SOURCE

  /* Glibc versions <= 2.19: */ _SVID_SOURCE || _BSD_SOURCE
```

DESCRIPTION

The `random()` function uses a nonlinear additive feedback random number generator employing a default table of size 31 long integers to return successive pseudo-random numbers in the range from 0 to $2^{31} - 1$. The period of this random number generator is very large, approximately $16 * ((2^{31}) - 1)$.

The `srandom()` function sets its argument as the seed for a new sequence of pseudo-random integers to be returned by `random()`. These sequences are repeatable by calling `srandom()` with the same seed value. If no

seed value is provided, the random() function is automatically seeded with a value of 1.

The initState() function allows a state array state to be initialized for use by random(). The size of the state array n is used by initState() to decide how sophisticated a random number generator it should use?the larger the state array, the better the random numbers will be. Current "optimal" values for the size of the state array n are 8, 32, 64, 128, and 256 bytes; other amounts will be rounded down to the nearest known amount. Using less than 8 bytes results in an error. seed is the seed for the initialization, which specifies a starting point for the random number sequence, and provides for restarting at the same point.

The setstate() function changes the state array used by the random() function. The state array state is used for random number generation until the next call to initState() or setstate(). state must first have been initialized using initState() or be the result of a previous call of setstate().

RETURN VALUE

The random() function returns a value between 0 and $(2^{31}) - 1$. The srandom() function returns no value.

The initState() function returns a pointer to the previous state array.

On error, errno is set to indicate the cause.

On success, setstate() returns a pointer to the previous state array.

On error, it returns NULL, with errno set to indicate the cause of the error.

ERRORS

EINVAL The state argument given to setstate() was NULL.

EINVAL A state array of less than 8 bytes was specified to initState().

ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

??

?Interface ? Attribute ? Value ?

??

?random(), srandom(), ? Thread safety ? MT-Safe ?

?initstate(), setstate() ? ? ?

??

CONFORMING TO

POSIX.1-2001, POSIX.1-2008, 4.3BSD.

NOTES

The random() function should not be used in multithreaded programs where reproducible behavior is required. Use random_r(3) for that purpose.

Random-number generation is a complex topic. Numerical Recipes in C: The Art of Scientific Computing (William H. Press, Brian P. Flannery, Saul A. Teukolsky, William T. Vetterling; New York: Cambridge University Press, 2007, 3rd ed.) provides an excellent discussion of practical random-number generation issues in Chapter 7 (Random Numbers). For a more theoretical discussion which also covers many practical issues in depth, see Chapter 3 (Random Numbers) in Donald E. Knuth's The Art of Computer Programming, volume 2 (Seminumerical Algorithms), 2nd ed.; Reading, Massachusetts: Addison-Wesley Publishing Company, 1981.

BUGS

According to POSIX, initstate() should return NULL on error. In the glibc implementation, errno is (as specified) set on error, but the function does not return NULL.

SEE ALSO

getrandom(2), drand48(3), rand(3), random_r(3), srand(3)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.