



Full credit is given to the above companies including the OS that this PDF file was generated!

Red Hat Enterprise Linux Release 9.2 Manual Pages on 'sysctl.8' command

\$ man sysctl.8

SYSCTL(8) System Administration SYSCTL(8)

NAME

sysctl - configure kernel parameters at runtime

SYNOPSIS

sysctl [options] [variable[=value]] [...]

sysctl -p [file or regexp] [...]

DESCRIPTION

sysctl is used to modify kernel parameters at runtime. The parameters available are those listed under /proc/sys/. Procfs is required for sysctl support in Linux. You can use sysctl to both read and write sysctl data.

PARAMETERS

variable

The name of a key to read from. An example is kernel.ostype.

The '/' separator is also accepted in place of a '.'.

variable=value

To set a key, use the form variable=value where variable is the key and value is the value to set it to. If the value contains quotes or characters which are parsed by the shell, you may need to enclose the value in double quotes.

-n, --values

Use this option to disable printing of the key name when printing values.

-e, --ignore

Use this option to ignore errors about unknown keys.

-N, --names

Use this option to only print the names. It may be useful with shells that have programmable completion.

-q, --quiet

Use this option to not display the values set to stdout.

-w, --write

Use this option when all arguments prescribe a key to be set.

-p[FILE], --load[=FILE]

Load in sysctl settings from the file specified or /etc/sysctl.conf if none given. Specifying - as filename means reading data from standard input. Using this option will mean arguments to sysctl are files, which are read in the order they are specified. The file argument may be specified as regular expression.

-a, --all

Display all values currently available.

--deprecated

Include deprecated parameters to --all values listing.

-b, --binary

Print value without new line.

--system

Load settings from all system configuration files. Files are read from directories in the following list in given order from top to bottom. Once a file of a given filename is loaded, any file of the same name in subsequent directories is ignored.

/etc/sysctl.d/*.conf

/run/sysctl.d/*.conf

/usr/local/lib/sysctl.d/*.conf

/usr/lib/sysctl.d/*.conf

/lib/sysctl.d/*.conf

/etc/sysctl.conf

`-r, --pattern pattern`

Only apply settings that match pattern. The pattern uses extended regular expression syntax.

`-A` Alias of `-a`

`-d` Alias of `-h`

`-f` Alias of `-p`

`-X` Alias of `-a`

`-o` Does nothing, exists for BSD compatibility.

`-x` Does nothing, exists for BSD compatibility.

`-h, --help`

Display help text and exit.

`-V, --version`

Display version information and exit.

EXAMPLES

```
/sbin/sysctl -a
```

```
/sbin/sysctl -n kernel.hostname
```

```
/sbin/sysctl -w kernel.domainname="example.com"
```

```
/sbin/sysctl -p/etc/sysctl.conf
```

```
/sbin/sysctl -a --pattern forward
```

```
/sbin/sysctl -a --pattern forward$
```

```
/sbin/sysctl -a --pattern 'net.ipv4.conf.(eth|wlan)0.arp'
```

```
/sbin/sysctl --system --pattern '^net.ipv6'
```

DEPRECATED PARAMETERS

The `base_reachable_time` and `retrans_time` are deprecated. The `sysctl` command does not allow changing values of these parameters. Users who insist to use deprecated kernel interfaces should push values to `/proc` file system by other means. For example:

```
echo 256 > /proc/sys/net/ipv6/neigh/eth0/base_reachable_time
```

FILES

```
/proc/sys
```

```
/etc/sysctl.d/*.conf
```

```
/run/sysctl.d/*.conf
```

```
/usr/local/lib/sysctl.d/*.conf
```

`/usr/lib/sysctl.d/*.conf`

`/lib/sysctl.d/*.conf`

`/etc/sysctl.conf`

SEE ALSO

`sysctl.conf(5)` `regex(7)`

AUTHOR

George Staikos [?staikos@0wned.org?](mailto:staikos@0wned.org)

REPORTING BUGS

Please send bug reports to [?procps@freelists.org?](mailto:procps@freelists.org)

procps-ng

2020-02-27

SYSCTL(8)