



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'matherr.3'

\$ man matherr.3

MATHERR(3) Linux Programmer's Manual MATHERR(3)

NAME

matherr - SVID math library exception handling

SYNOPSIS

```
#include <math.h>

int matherr(struct exception *exc);

extern _LIB_VERSION_TYPE _LIB_VERSION;
```

Link with -lm.

DESCRIPTION

Note: the mechanism described in this page is no longer supported by glibc. Before glibc 2.27, it had been marked as obsolete. Since glibc 2.27, the mechanism has been removed altogether. New applications should use the techniques described in math_error(7) and fenv(3). This page documents the matherr() mechanism as an aid for maintaining and porting older applications.

The System V Interface Definition (SVID) specifies that various math functions should invoke a function called matherr() if a math exception is detected. This function is called before the math function returns;

after `matherr()` returns, the system then returns to the math function,

which in turn returns to the caller.

To employ `matherr()`, the programmer must define the `_SVID_SOURCE` feature test macro (before including any header files), and assign the value `_SVID_` to the external variable `_LIB_VERSION`.

The system provides a default version of `matherr()`. This version does nothing, and returns zero (see below for the significance of this).

The default `matherr()` can be overridden by a programmer-defined version, which will be invoked when an exception occurs. The function is invoked with one argument, a pointer to an exception structure, defined as follows:

```
struct exception {  
    int type; /* Exception type */  
    char *name; /* Name of function causing exception */  
    double arg1; /* 1st argument to function */  
    double arg2; /* 2nd argument to function */  
    double retval; /* Function return value */  
}
```

The type field has one of the following values:

DOMAIN A domain error occurred (the function argument was outside the range for which the function is defined). The return value depends on the function; `errno` is set to `EDOM`.

SING A pole error occurred (the function result is an infinity).

The return value in most cases is `HUGE` (the largest single precision floating-point number), appropriately signed. In most cases, `errno` is set to `EDOM`.

OVERFLOW An overflow occurred. In most cases, the value `HUGE` is returned, and `errno` is set to `ERANGE`.

UNDERFLOW An underflow occurred. `0.0` is returned, and `errno` is set to `ERANGE`.

TLOSS Total loss of significance. `0.0` is returned, and `errno` is set to `ERANGE`.

PLOSS Partial loss of significance. This value is unused on

glibc (and many other systems).

The arg1 and arg2 fields are the arguments supplied to the function (arg2 is undefined for functions that take only one argument).

The retval field specifies the return value that the math function will return to its caller. The programmer-defined matherr() can modify this field to change the return value of the math function.

If the matherr() function returns zero, then the system sets errno as described above, and may print an error message on standard error (see below).

If the matherr() function returns a nonzero value, then the system does not set errno, and doesn't print an error message.

Math functions that employ matherr()

The table below lists the functions and circumstances in which math? err() is called. The "Type" column indicates the value assigned to exc->type when calling matherr(). The "Result" column is the default return value assigned to exc->retval.

The "Msg?" and "errno" columns describe the default behavior if math? err() returns zero. If the "Msg?" column contains "y", then the sys? tem prints an error message on standard error.

The table uses the following notations and abbreviations:

x first argument to function

y second argument to function

fin finite value for argument

neg negative value for argument

int integral value for argument

o/f result overflowed

u/f result underflowed

|x| absolute value of x

X_TLOSS is a constant defined in <math.h>

Function	Type	Result	Msg?	errno
acos(x >1)	DOMAIN	HUGE	y	EDOM
asin(x >1)	DOMAIN	HUGE	y	EDOM
atan2(0,0)	DOMAIN	HUGE	y	EDOM

acosh(x<1)	DOMAIN	NAN	y	EDOM
atanh(x >1)	DOMAIN	NAN	y	EDOM
atanh(x ==1)	SING	(x>0.0)?	y	EDOM
	HUGE_VAL :			
	-HUGE_VAL			
cosh(fin) o/f	OVERFLOW	HUGE	n	ERANGE
sinh(fin) o/f	OVERFLOW	(x>0.0) ?	n	ERANGE
	HUGE : -HUGE			
sqrt(x<0)	DOMAIN	0.0	y	EDOM
hypot(fin,fin) o/f	OVERFLOW	HUGE	n	ERANGE
exp(fin) o/f	OVERFLOW	HUGE	n	ERANGE
exp(fin) u/f	UNDERFLOW	0.0	n	ERANGE
exp2(fin) o/f	OVERFLOW	HUGE	n	ERANGE
exp2(fin) u/f	UNDERFLOW	0.0	n	ERANGE
exp10(fin) o/f	OVERFLOW	HUGE	n	ERANGE
exp10(fin) u/f	UNDERFLOW	0.0	n	ERANGE
j0(x >X_TLOSS)	TLOSS	0.0	y	ERANGE
j1(x >X_TLOSS)	TLOSS	0.0	y	ERANGE
jn(x >X_TLOSS)	TLOSS	0.0	y	ERANGE
y0(x>X_TLOSS)	TLOSS	0.0	y	ERANGE
y1(x>X_TLOSS)	TLOSS	0.0	y	ERANGE
yn(x>X_TLOSS)	TLOSS	0.0	y	ERANGE
y0(0)	DOMAIN	-HUGE	y	EDOM
y0(x<0)	DOMAIN	-HUGE	y	EDOM
y1(0)	DOMAIN	-HUGE	y	EDOM
y1(x<0)	DOMAIN	-HUGE	y	EDOM
yn(n,0)	DOMAIN	-HUGE	y	EDOM
yn(x<0)	DOMAIN	-HUGE	y	EDOM
lgamma(fin) o/f	OVERFLOW	HUGE	n	ERANGE
lgamma(-int) or	SING	HUGE	y	EDOM
lgamma(0)				
tgamma(fin) o/f	OVERFLOW	HUGE_VAL	n	ERANGE
tgamma(-int)	SING	NAN	y	EDOM

tgamma(0)	SING	copysign(y	ERANGE
		HUGE_VAL,x)		
log(0)	SING	-HUGE	y	EDOM
log(x<0)	DOMAIN	-HUGE	y	EDOM
log2(0)	SING	-HUGE	n	EDOM
log2(x<0)	DOMAIN	-HUGE	n	EDOM
log10(0)	SING	-HUGE	y	EDOM
log10(x<0)	DOMAIN	-HUGE	y	EDOM
pow(0.0,0.0)	DOMAIN	0.0	y	EDOM
pow(x,y) o/f	OVERFLOW	HUGE	n	ERANGE
pow(x,y) u/f	UNDERFLOW	0.0	n	ERANGE
pow(NaN,0.0)	DOMAIN	x	n	EDOM
0**neg	DOMAIN	0.0	y	EDOM
neg**non-int	DOMAIN	0.0	y	EDOM
scalb() o/f	OVERFLOW	(x>0.0) ?	n	ERANGE
		HUGE_VAL :		
		-HUGE_VAL		
scalb() u/f	UNDERFLOW	copysign(n	ERANGE
		0.0,x)		
fmod(x,0)	DOMAIN	x	y	EDOM
remainder(x,0)	DOMAIN	NAN	y	EDOM

ATTRIBUTES

For an explanation of the terms used in this section, see at?

tributes(7).

??

?Interface ? Attribute ? Value ?

??

?matherr() ? Thread safety ? MT-Safe ?

??

EXAMPLES

The example program demonstrates the use of matherr() when calling log(3). The program takes up to three command-line arguments. The first argument is the floating-point number to be given to log(3). If

the optional second argument is provided, then `_LIB_VERSION` is set to `_SVID_` so that `matherr()` is called, and the integer supplied in the command-line argument is used as the return value from `matherr()`. If the optional third command-line argument is supplied, then it specifies an alternative return value that `matherr()` should assign as the return value of the math function.

The following example run, where `log(3)` is given an argument of 0.0, does not use `matherr()`:

```
$ ./a.out 0.0  
errno: Numerical result out of range  
x=-inf
```

In the following run, `matherr()` is called, and returns 0:

```
$ ./a.out 0.0 0  
matherr SING exception in log() function  
args: 0.000000, 0.000000  
retval: -340282346638528859811704183484516925440.000000  
log: SING error  
errno: Numerical argument out of domain  
x=-340282346638528859811704183484516925440.000000
```

The message "log: SING error" was printed by the C library.

In the following run, `matherr()` is called, and returns a nonzero value:

```
$ ./a.out 0.0 1  
matherr SING exception in log() function  
args: 0.000000, 0.000000  
retval: -340282346638528859811704183484516925440.000000  
x=-340282346638528859811704183484516925440.000000
```

In this case, the C library did not print a message, and `errno` was not set.

In the following run, `matherr()` is called, changes the return value of the math function, and returns a nonzero value:

```
$ ./a.out 0.0 1 12345.0  
matherr SING exception in log() function  
args: 0.000000, 0.000000
```

retval: -340282346638528859811704183484516925440.000000

x=12345.000000

Program source

```
#define _SVID_SOURCE

#include <errno.h>
#include <math.h>
#include <stdio.h>
#include <stdlib.h>

static int matherr_ret = 0; /* Value that matherr()
                                should return */

static int change(retval = 0; /* Should matherr() change
                                function's return value? */

static double new_retval; /* New function return value */

int
matherr(struct exception *exc)
{
    fprintf(stderr, "matherr %s exception in %s() function\n",
            (exc->type == DOMAIN) ? "DOMAIN" :
            (exc->type == OVERFLOW) ? "OVERFLOW" :
            (exc->type == UNDERFLOW) ? "UNDERFLOW" :
            (exc->type == SING) ? "SING" :
            (exc->type == TLOSS) ? "TLOSS" :
            (exc->type == PLOSS) ? "PLOSS" : "???",

            exc->name);

    fprintf(stderr, "      args: %f, %f\n",
            exc->arg1, exc->arg2);

    fprintf(stderr, "      retval: %f\n", exc->retval);

    if (change_retval)
        exc->retval = new_retval;

    return matherr_ret;
}

main(int argc, char *argv[])
}
```

```
{  
    double x;  
  
    if (argc < 2) {  
        fprintf(stderr, "Usage: %s <argval>"  
                " [<matherr-ret> [<new-func-retval>]]\n", argv[0]);  
        exit(EXIT_FAILURE);  
    }  
  
    if (argc > 2) {  
        _LIB_VERSION = _SVID_;  
        matherr_ret = atoi(argv[2]);  
    }  
  
    if (argc > 3) {  
        change_retval = 1;  
        new_retval = atof(argv[3]);  
    }  
  
    x = log(atof(argv[1]));  
    if (errno != 0)  
        perror("errno");  
    printf("x=%f\n", x);  
    exit(EXIT_SUCCESS);  
}
```

SEE ALSO

fenv(3), math_error(7), standards(7)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at
<https://www.kernel.org/doc/man-pages/>.