

Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'modules-load.d.5'

\$ man modules-load.d.5

MODULES-LOAD.D(5)

modules-load.d

MODULES-LOAD.D(5)

NAME

modules-load.d - Configure kernel modules to load at boot

SYNOPSIS

/etc/modules-load.d/*.conf

/run/modules-load.d/*.conf

/usr/lib/modules-load.d/*.conf

DESCRIPTION

systemd-modules-load.service(8) reads files from the above directories which contain kernel modules to load during boot in a static list. Each configuration file is named in the style of /etc/modules-load.d/program.conf. Note that it is usually a better idea to rely on the automatic module loading by PCI IDs, USB IDs, DMI IDs or

similar triggers encoded in the kernel modules themselves instead of static configuration like this. In fact, most modern kernel modules are prepared for automatic loading already.

CONFIGURATION FORMAT

The configuration files should simply contain a list of kernel module names to load, separated by newlines. Empty lines and lines whose first non-whitespace character is # or ; are ignored.

CONFIGURATION DIRECTORIES AND PRECEDENCE

Configuration files are read from directories in /etc/, /run/, /usr/local/lib/, and /usr/lib/, in order of precedence, as listed in the SYNOPSIS section above. Files must have the ".conf" extension. Files in /etc/ override files with the same name in /run/, /usr/local/lib/, and /usr/lib/. Files in /run/ override files with the same name under /usr/.

All configuration files are sorted by their filename in lexicographic order, regardless of which of the directories they reside in. If multiple files specify the same option, the entry in the file with the lexicographically latest name will take precedence. Thus, the configuration in a certain file may either be replaced completely (by placing a file with the same name in a directory with higher priority), or individual settings might be changed (by specifying additional settings in a file with a different name that is ordered later).

Packages should install their configuration files in /usr/lib/
(distribution packages) or /usr/local/lib/ (local installs). Files in
/etc/ are reserved for the local administrator, who may use this logic
to override the configuration files installed by vendor packages. It is
recommended to prefix all filenames with a two-digit number and a dash,
to simplify the ordering of the files.

If the administrator wants to disable a configuration file supplied by the vendor, the recommended way is to place a symlink to /dev/null in the configuration directory in /etc/, with the same filename as the vendor configuration file. If the vendor configuration file is included in the initrd image, the image has to be regenerated.

EXAMPLE

Example 1. /etc/modules-load.d/virtio-net.conf example:

Load virtio-net.ko at boot virtio-net

SEE ALSO

systemd(1), systemd-modules-load.service(8), systemd-delta(1),
modprobe(8)

systemd 252

MODULES-LOAD.D(5)