## NAME

openssl-asn1parse, asn1parse - ASN.1 parsing tool

## SYNOPSIS

openssl asn1parse [-help] [-inform PEM|DER] [-in filename] [-out filename] [-noout] [-offset number] [-length number] [-i] [-oid filename] [-dump] [-dlimit num] [-strparse offset] [-genstr string] [-genconf file] [-strictpem] [-item name]

## DESCRIPTION

The **asn1parse** command is a diagnostic utility that can parse ASN.1 structures. It can also be used to extract data from ASN.1 formatted data.

## **OPTIONS**

# -help

Print out a usage message.

### -inform DER|PEM

The input format. DER is binary format and PEM (the default) is base64 encoded.

### -in filename

The input file, default is standard input.

### -out filename

Output file to place the DER encoded data into. If this option is not present then no data will be output. This is most useful when combined with the **-strparse** option.

#### -noout

Don't output the parsed version of the input file.

#### -offset number

Starting offset to begin parsing, default is start of file.

#### -length number

Number of bytes to parse, default is until end of file.

-i Indents the output according to the "depth" of the structures.

#### -oid filename

A file containing additional OBJECT IDENTIFIERs (OIDs). The format of this file is described in the NOTES section below.

# -dump

Dump unknown data in hex format.

#### -dlimit num

Like -dump, but only the first num bytes are output.

## -strparse offset

Parse the contents octets of the ASN.1 object starting at **offset**. This option can be used multiple times to "drill down" into a nested structure.

## -genstr string, -genconf file

Generate encoded data based on **string**, **file** or both using **ASN1\_generate\_nconf**(3) format. If **file** only is present then the string is obtained from the default section using the name **asn1**. The encoded data is passed through the ASN1 parser and printed out as though it came from a file, the contents can thus be examined and written to a file using the **out** option.

#### -strictpem

If this option is used then **-inform** will be ignored. Without this option any data in a PEM format input file will be treated as being base64 encoded and processed whether it has the normal PEM BEGIN and END markers or not. This option will ignore any data prior to the start of the BEGIN marker, or after an END marker in a PEM file.

#### -item name

Attempt to decode and print the data as **ASN1\_ITEM name**. This can be used to print out the fields of any supported ASN.1 structure if the type is known.

#### Output

The output will typically contain lines like this:

```
0:d=0 hl=4 l= 681 cons: SEOUENCE
.....
 229:d=3 hl=3 l= 141 prim: BIT STRING
 373:d=2 hl=3 l= 162 cons: cont [ 3 ]
 376:d=3 hl=3 l= 159 cons: SEQUENCE
 379:d=4 hl=2 l= 29 cons: SEQUENCE
 381:d=5 hl=2 l=
                  3 prim: OBJECT
                                              :X509v3 Subject Key Identifier
 386:d=5 hl=2 l= 22 prim: OCTET STRING
 410:d=4 hl=2 l= 112 cons: SEQUENCE
 412:d=5 hl=2 l=
                    3 prim: OBJECT
                                              :X509v3 Authority Key Identifier
 417:d=5 hl=2 l= 105 prim: OCTET STRING
 524:d=4 hl=2 l= 12 cons: SEQUENCE
```

•••••

This example is part of a self-signed certificate. Each line starts with the offset in decimal. **d=XX** specifies the current depth. The depth is increased within the scope of any SET or SEQUENCE. **hl=XX** gives the header length (tag and length octets) of the current type. **l=XX** gives the length of the contents octets.

The -i option can be used to make the output more readable.

Some knowledge of the ASN.1 structure is needed to interpret the output.

In this example the BIT STRING at offset 229 is the certificate public key. The contents octets of this will contain the public key information. This can be examined using the option **–strparse 229** to yield:

0:d=0	hl=3 l= 1	.37 cons:	SEQUENCE	
3:d=1	hl=3 l= 1	29 prim:	INTEGER	:E5D21E1F5C8D208EA7A2166C7FAF9F6BDF20
135:d=1	hl=2 l=	3 prim:	INTEGER	:010001

### NOTES

If an OID is not part of OpenSSL's internal table it will be represented in numerical form (for example 1.2.3.4). The file passed to the **-oid** option allows additional OIDs to be included. Each line consists of three columns, the first column is the OID in numerical format and should be followed by white space. The second column is the "short name" which is a single word followed by white space. The final column is the rest of the line and is the "long name". **asn1parse** displays the long name. Example:

1.2.3.4 shortName A long name

#### **EXAMPLES**

Parse a file:

openssl asn1parse -in file.pem

Parse a DER file:

openssl asn1parse -inform DER -in file.der

Generate a simple UTF8String:

openssl asn1parse -genstr 'UTF8:Hello World'

Generate and write out a UTF8String, don't print parsed output:

```
openssl asn1parse -genstr 'UTF8:Hello World' -noout -out utf8.der
```

Generate using a config file:

openssl asn1parse -genconf asn1.cnf -noout -out asn1.der

Example config file:

asn1=SEQUENCE:seq\_sect

[seq\_sect]

field1=BOOL:TRUE
field2=EXP:0, UTF8:some random string

### BUGS

There should be options to change the format of output lines. The output of some ASN.1 types is not well handled (if at all).

# SEE ALSO

ASN1\_generate\_nconf(3)

# COPYRIGHT

Copyright 2000–2017 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the OpenSSL license (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <a href="https://www.openssl.org/source/license.html">https://www.openssl.org/source/license.html</a>>.