

# Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

## Rocky Enterprise Linux 9.2 Manual Pages on command 'add\_key.2'

## \$ man add\_key.2

ADD\_KEY(2)

2) Linux Key Management Calls

ADD\_KEY(2)

## NAME

add\_key - add a key to the kernel's key management facility

## SYNOPSIS

#include <sys/types.h>

#include <keyutils.h>

key\_serial\_t add\_key(const char \*type, const char \*description,

const void \*payload, size\_t plen,

key\_serial\_t keyring);

No glibc wrapper is provided for this system call; see NOTES.

## DESCRIPTION

add\_key() creates or updates a key of the given type and description, instantiates it with the payload of length plen, attaches it to the nominated keyring, and returns the key's serial number.

The key may be rejected if the provided data is in the wrong format or it is invalid in some other way.

If the destination keyring already contains a key that matches the specified type and de? scription, then, if the key type supports it, that key will be updated rather than a new key being created; if not, a new key (with a different ID) will be created and it will displace the link to the extant key from the keyring.

The destination keyring serial number may be that of a valid keyring for which the caller has write permission. Alternatively, it may be one of the following special keyring IDs:

## KEY\_SPEC\_THREAD\_KEYRING

This specifies the caller's thread-specific keyring (thread-keyring(7)).

#### KEY\_SPEC\_PROCESS\_KEYRING

This specifies the caller's process-specific keyring (process-keyring(7)).

#### KEY\_SPEC\_SESSION\_KEYRING

This specifies the caller's session-specific keyring (session-keyring(7)).

#### KEY\_SPEC\_USER\_KEYRING

This specifies the caller's UID-specific keyring (user-keyring(7)).

#### KEY\_SPEC\_USER\_SESSION\_KEYRING

This specifies the caller's UID-session keyring (user-session-keyring(7)).

## Key types

The key type is a string that specifies the key's type. Internally, the kernel defines a number of key types that are available in the core key management code. Among the types that are available for user-space use and can be specified as the type argument to add\_key() are the following:

### "keyring"

Keyrings are special key types that may contain links to sequences of other keys of any type. If this interface is used to create a keyring, then payload should be

NULL and plen should be zero.

"user" This is a general purpose key type whose payload may be read and updated by userspace applications. The key is kept entirely within kernel memory. The payload for keys of this type is a blob of arbitrary data of up to 32,767 bytes.

"logon" (since Linux 3.3)

This key type is essentially the same as "user", but it does not permit the key to read. This is suitable for storing payloads that you do not want to be readable from user space.

This key type vets the description to ensure that it is qualified by a "service" prefix, by checking to ensure that the description contains a ':' that is preceded by other char? acters.

"big\_key" (since Linux 3.13)

This key type is similar to "user", but may hold a payload of up to 1 MiB. If the key payload is large enough, then it may be stored encrypted in tmpfs (which can be swapped out) rather than kernel memory.

For further details on these key types, see keyrings(7).

#### **RETURN VALUE**

On success, add\_key() returns the serial number of the key it created or updated. On er?

ror, -1 is returned and errno is set to indicate the cause of the error.

#### ERRORS

EACCES The keyring wasn't available for modification by the user.

EDQUOT The key quota for this user would be exceeded by creating this key or linking it to

the keyring.

EFAULT One or more of type, description, and payload points outside process's accessible address space.

EINVAL The size of the string (including the terminating null byte) specified in type or

description exceeded the limit (32 bytes and 4096 bytes respectively).

EINVAL The payload data was invalid.

EINVAL type was "logon" and the description was not qualified with a prefix string of the form "service:".

#### EKEYEXPIRED

The keyring has expired.

#### **EKEYREVOKED**

The keyring has been revoked.

ENOKEY The keyring doesn't exist.

ENOMEM Insufficient memory to create a key.

EPERM The type started with a period ('.'). Key types that begin with a period are re? served to the implementation.

EPERM type was "keyring" and the description started with a period ('.'). Keyrings with descriptions (names) that begin with a period are reserved to the implementation.

#### VERSIONS

This system call first appeared in Linux 2.6.10.

#### CONFORMING TO

This system call is a nonstandard Linux extension.

#### NOTES

No wrapper for this system call is provided in glibc. A wrapper is provided in the libkeyutils package. When employing the wrapper in that library, link with -lkeyutils.

## **EXAMPLES**

The program below creates a key with the type, description, and payload specified in its

command-line arguments, and links that key into the session keyring. The following shell session demonstrates the use of the program:

\$ ./a.out user mykey "Some payload"

Key ID is 64a4dca

\$ grep '64a4dca' /proc/keys

064a4dca I--Q--- 1 perm 3f010000 1000 1000 user mykey: 12

## Program source

#include <sys/types.h>

#include <keyutils.h>

#include <stdint.h>

#include <stdio.h>

#include <stdlib.h>

#include <string.h>

int

main(int argc, char \*argv[])

## {

```
key_serial_t key;
```

```
if (argc != 4) {
```

fprintf(stderr, "Usage: %s type description payload\n",

argv[0]);

exit(EXIT\_FAILURE);

}

key = add\_key(argv[1], argv[2], argv[3], strlen(argv[3]),

KEY\_SPEC\_SESSION\_KEYRING);

```
if (key == -1) {
```

```
perror("add_key");
```

```
exit(EXIT_FAILURE);
```

```
}
```

```
printf("Key ID is %jx\n", (uintmax_t) key);
```

```
exit(EXIT_SUCCESS);
```

## }

## SEE ALSO

persistent-keyring(7), process-keyring(7), session-keyring(7), thread-keyring(7),

user-keyring(7), user-session-keyring(7)

The kernel source files Documentation/security/keys/core.rst and

Documentation/keys/request-key.rst (or, before Linux 4.13, in the files

Documentation/security/keys.txt and Documentation/security/keys-request-key.txt).

## COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux

2020-11-01

ADD\_KEY(2)