



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'frexpf.3'

\$ man frexpf.3

FREXP(3) Linux Programmer's Manual FREXP(3)

NAME

frexp, frexpf, frexpl - convert floating-point number to fractional and integral components

SYNOPSIS

```
#include <math.h>

double frexp(double x, int *exp);

float frexpf(float x, int *exp);

long double frexpl(long double x, int *exp);
```

Link with -lm.

Feature Test Macro Requirements for glibc (see feature_test_macros(7)):

```
frexpf(), frexpl():

    _ISOC99_SOURCE || _POSIX_C_SOURCE >= 200112L

    /* Since glibc 2.19: */ _DEFAULT_SOURCE

    /* Glibc versions <= 2.19: */ _BSD_SOURCE || _SVID_SOURCE
```

DESCRIPTION

These functions are used to split the number *x* into a normalized fraction and an exponent which is stored in *exp*.

RETURN VALUE

These functions return the normalized fraction. If the argument *x* is not zero, the normalized fraction is *x* times a power of two, and its absolute value is always in the range 1/2 (inclusive) to 1 (exclusive), that is, [0.5,1).

If *x* is zero, then the normalized fraction is zero and zero is stored in *exp*.

If x is a NaN, a NaN is returned, and the value of *exp is unspecified.

If x is positive infinity (negative infinity), positive infinity (negative infinity) is returned, and the value of *exp is unspecified.

ERRORS

No errors occur.

ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

??

?Interface ? Attribute ? Value ?

??

?frexpl(), frexpf(), frexpl() ? Thread safety ? MT-Safe ?

??

CONFORMING TO

C99, POSIX.1-2001, POSIX.1-2008.

The variant returning double also conforms to SVr4, 4.3BSD, C89.

EXAMPLES

The program below produces results such as the following:

```
$ ./a.out 2560
```

```
frexp(2560, &e) = 0.625: 0.625 * 2^12 = 2560
```

```
$ ./a.out -4
```

```
frexp(-4, &e) = -0.5: -0.5 * 2^3 = -4
```

Program source

```
#include <math.h>
#include <float.h>
#include <stdio.h>
#include <stdlib.h>

int
main(int argc, char *argv[])
{
    double x, r;
    int exp;
    x = strtod(argv[1], NULL);
    r = frexp(x, &exp);
```

```
printf("frexp(%g, &e) = %g: %g * %d^%d = %g\n",
      x, r, r, FLT_RADIX, exp, x);
exit(EXIT_SUCCESS);
}
```

SEE ALSO

ldexp(3), modf(3)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

2020-06-09

FREXP(3)