

Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

# Rocky Enterprise Linux 9.2 Manual Pages on command 'process\_vm\_writev.2'

# \$ man process\_vm\_writev.2

PROCESS\_VM\_READV(2)

Linux Programmer's Manual

PROCESS\_VM\_READV(2)

NAME

process\_vm\_readv, process\_vm\_writev - transfer data between process address spaces

### **SYNOPSIS**

9 ,

const struct iovec \*remote\_iov,

unsigned long riovent,

unsigned long flags);

Feature Test Macro Requirements for glibc (see feature\_test\_macros(7)):

process\_vm\_readv(), process\_vm\_writev():

\_GNU\_SOURCE

## **DESCRIPTION**

These system calls transfer data between the address space of the calling process ("the local process") and the process identified by pid ("the remote process"). The data moves

directly between the address spaces of the two processes, without passing through kernel space.

The process\_vm\_readv() system call transfers data from the remote process to the local process. The data to be transferred is identified by remote\_iov and riovcnt: remote\_iov is a pointer to an array describing address ranges in the process pid, and riovcnt speci? fies the number of elements in remote\_iov. The data is transferred to the locations spec? ified by local\_iov and liovcnt: local\_iov is a pointer to an array describing address ranges in the calling process, and liovcnt specifies the number of elements in local\_iov. The process\_vm\_writev() system call is the converse of process\_vm\_readv()?it transfers data from the local process to the remote process. Other than the direction of the trans? fer, the arguments liovcnt, local\_iov, riovcnt, and remote\_iov have the same meaning as for process\_vm\_readv().

The local\_iov and remote\_iov arguments point to an array of iovec structures, defined in <sys/uio.h> as:

```
struct iovec {
  void *iov_base; /* Starting address */
  size_t iov_len; /* Number of bytes to transfer */
};
```

Buffers are processed in array order. This means that process\_vm\_readv() completely fills local\_iov[0] before proceeding to local\_iov[1], and so on. Likewise, remote\_iov[0] is completely read before proceeding to remote\_iov[1], and so on.

Similarly, process\_vm\_writev() writes out the entire contents of local\_iov[0] before pro? ceeding to local\_iov[1], and it completely fills remote\_iov[0] before proceeding to re? mote\_iov[1].

The lengths of remote\_iov[i].iov\_len and local\_iov[i].iov\_len do not have to be the same.

Thus, it is possible to split a single local buffer into multiple remote buffers, or vice versa.

The flags argument is currently unused and must be set to 0.

The values specified in the liovcnt and riovcnt arguments must be less than or equal to IOV\_MAX (defined in limits.h> or accessible via the call sysconf(\_SC\_IOV\_MAX)).

The count arguments and local\_iov are checked before doing any transfers. If the counts are too big, or local\_iov is invalid, or the addresses refer to regions that are inacces? sible to the local process, none of the vectors will be processed and an error will be re?

turned immediately.

Note, however, that these system calls do not check the memory regions in the remote process until just before doing the read/write. Consequently, a partial read/write (see RETURN VALUE) may result if one of the remote\_iov elements points to an invalid memory re? gion in the remote process. No further reads/writes will be attempted beyond that point. Keep this in mind when attempting to read data of unknown length (such as C strings that are null-terminated) from a remote process, by avoiding spanning memory pages (typically 4 KiB) in a single remote iovec element. (Instead, split the remote read into two re? mote\_iov elements and have them merge back into a single write local\_iov entry. The first read entry goes up to the page boundary, while the second starts on the next page bound? ary.)

Permission to read from or write to another process is governed by a ptrace access mode PTRACE\_MODE\_ATTACH\_REALCREDS check; see ptrace(2).

#### **RETURN VALUE**

On success, process\_vm\_readv() returns the number of bytes read and process\_vm\_writev() returns the number of bytes written. This return value may be less than the total number of requested bytes, if a partial read/write occurred. (Partial transfers apply at the granularity of iovec elements. These system calls won't perform a partial transfer that splits a single iovec element.) The caller should check the return value to determine whether a partial read/write occurred.

On error, -1 is returned and errno is set appropriately.

### **ERRORS**

EFAULT The memory described by local\_iov is outside the caller's accessible address space.

EFAULT The memory described by remote\_iov is outside the accessible address space of the process pid.

EINVAL The sum of the iov\_len values of either local\_iov or remote\_iov overflows a ssize\_t value.

EINVAL flags is not 0.

EINVAL liovent or riovent is too large.

ENOMEM Could not allocate memory for internal copies of the iovec structures.

EPERM The caller does not have permission to access the address space of the process pid.

ESRCH No process with ID pid exists.

VERSIONS Page 3/5

These system calls were added in Linux 3.2. Support is provided in glibc since version 2.15.

#### **CONFORMING TO**

These system calls are nonstandard Linux extensions.

#### **NOTES**

The data transfers performed by process\_vm\_readv() and process\_vm\_writev() are not guaran? teed to be atomic in any way.

These system calls were designed to permit fast message passing by allowing messages to be exchanged with a single copy operation (rather than the double copy that would be required when using, for example, shared memory or pipes).

#### **EXAMPLES**

return 1;

The following code sample demonstrates the use of process\_vm\_readv(). It reads 20 bytes at the address 0x10000 from the process with PID 10 and writes the first 10 bytes into buf1 and the second 10 bytes into buf2.

```
#include <sys/uio.h>
int
main(void)
{
  struct iovec local[2];
  struct iovec remote[1];
  char buf1[10];
  char buf2[10];
  ssize_t nread;
                       /* PID of remote process */
  pid_t pid = 10;
  local[0].iov_base = buf1;
  local[0].iov len = 10;
  local[1].iov_base = buf2;
  local[1].iov_len = 10;
  remote[0].iov\_base = (void *) 0x10000;
  remote[0].iov_len = 20;
  nread = process_vm_readv(pid, local, 2, remote, 1, 0);
  if (nread != 20)
```

```
else
return 0;
}
SEE ALSO
readv(2), writev(2)
```

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux 2020-06-09

PROCESS\_VM\_READV(2)