

## Full credit is given to the above companies including the **Operating System (OS) that this PDF file was generated!**

# Rocky Enterprise Linux 9.2 Manual Pages on command 'tgammal.3'

## \$ man tgammal.3

TGAMMA(3)

Linux Programmer's Manual

TGAMMA(3)

## NAME

tgamma, tgammaf, tgammal - true gamma function

## **SYNOPSIS**

#include <math.h>

double tgamma(double x);

float tgammaf(float x);

long double tgammal(long double x);

Link with -Im.

Feature Test Macro Requirements for glibc (see feature\_test\_macros(7)):

tgamma(), tgammaf(), tgammal():

\_ISOC99\_SOURCE || \_POSIX\_C\_SOURCE >= 200112L

#### DESCRIPTION

These functions calculate the Gamma function of x.

The Gamma function is defined by

 $Gamma(x) = integral from 0 to infinity of t^(x-1) e^{-t} dt$ 

It is defined for every real number except for nonpositive integers. For nonnegative in?

tegral m one has

Gamma(m+1) = m!

and, more generally, for all x:

Gamma(x+1) = x \* Gamma(x)

Furthermore, the following is valid for all values of x outside the poles:

Gamma(x) \* Gamma(1 - x) = PI / sin(PI \* x)

#### **RETURN VALUE**

On success, these functions return Gamma(x).

If x is a NaN, a NaN is returned.

If x is positive infinity, positive infinity is returned.

If x is a negative integer, or is negative infinity, a domain error occurs, and a NaN is returned.

If the result overflows, a range error occurs, and the functions return HUGE\_VAL,

HUGE\_VALF, or HUGE\_VALL, respectively, with the correct mathematical sign.

If the result underflows, a range error occurs, and the functions return 0, with the cor? rect mathematical sign.

If x is -0 or +0, a pole error occurs, and the functions return HUGE\_VAL, HUGE\_VALF, or

HUGE\_VALL, respectively, with the same sign as the 0.

#### ERRORS

See math\_error(7) for information on how to determine whether an error has occurred when calling these functions.

The following errors can occur:

Domain error: x is a negative integer, or negative infinity

errno is set to EDOM. An invalid floating-point exception (FE\_INVALID) is raised

(but see BUGS).

Pole error: x is +0 or -0

errno is set to ERANGE. A divide-by-zero floating-point exception (FE\_DIVBYZERO)

is raised.

Range error: result overflow

errno is set to ERANGE. An overflow floating-point exception (FE\_OVERFLOW) is

raised.

glibc also gives the following error which is not specified in C99 or POSIX.1-2001.

Range error: result underflow

An underflow floating-point exception (FE\_UNDERFLOW) is raised, and errno is set to

ERANGE.

#### VERSIONS

These functions first appeared in glibc in version 2.1.

#### ATTRIBUTES

For an explanation of the terms used in this section, see attributes(7).

#### 

?Interface ? Attribute ? Value ?

## 

?tgamma(), tgammaf(), tgammal() ? Thread safety ? MT-Safe ?

## CONFORMING TO

C99, POSIX.1-2001, POSIX.1-2008.

## NOTES

This function had to be called "true gamma function" since there is already a function gamma(3) that returns something else (see gamma(3) for details).

## BUGS

Before version 2.18, the glibc implementation of these functions did not set errno to EDOM when x is negative infinity.

Before glibc 2.19, the glibc implementation of these functions did not set errno to ERANGE on an underflow range error. x

In glibc versions 2.3.3 and earlier, an argument of +0 or -0 incorrectly produced a domain error (errno set to EDOM and an FE\_INVALID exception raised), rather than a pole error.

#### SEE ALSO

gamma(3), Igamma(3)

#### COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

GNU

2017-09-15

TGAMMA(3)