



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'vmsplice.2'

\$ man vmsplice.2

VMSPLICE(2) Linux Programmer's Manual VMSPLICE(2)

NAME

vmsplice - splice user pages to/from a pipe

SYNOPSIS

```
#define _GNU_SOURCE        /* See feature_test_macros(7) */  
  
#include <fcntl.h>  
  
#include <sys/uio.h>  
  
ssize_t vmsplice(int fd, const struct iovec *iov,  
                  unsigned long nr_segs, unsigned int flags);
```

DESCRIPTION

If `fd` is opened for writing, the `vmsplice()` system call maps `nr_segs` ranges of user memory described by `iov` into a pipe. If `fd` is opened for reading, the `vmsplice()` system call fills `nr_segs` ranges of user memory described by `iov` from a pipe. The file descriptor `fd` must refer to a pipe.

The pointer `iov` points to an array of `iovec` structures as defined in `<sys/uio.h>`:

```
struct iovec {  
    void *iov_base;        /* Starting address */  
    size_t iov_len;       /* Number of bytes */  
};
```

The `flags` argument is a bit mask that is composed by ORing together zero or more of the following values:

SPLICE_F_MOVE

Unused for `vmsplice()`; see `splice(2)`.

SPLICE_F_NONBLOCK

Do not block on I/O; see splice(2) for further details.

SPLICE_F_MORE

Currently has no effect for vmsplice(), but may be implemented in the future; see splice(2).

SPLICE_F_GIFT

The user pages are a gift to the kernel. The application may not modify this memory ever, otherwise the page cache and on-disk data may differ. Gifting pages to the kernel means that a subsequent splice(2) SPLICE_F_MOVE can successfully move the pages; if this flag is not specified, then a subsequent splice(2) SPLICE_F_MOVE must copy the pages. Data must also be properly page aligned, both in memory and length.

RETURN VALUE

Upon successful completion, vmsplice() returns the number of bytes transferred to the pipe. On error, vmsplice() returns -1 and errno is set to indicate the error.

ERRORS

EAGAIN SPLICE_F_NONBLOCK was specified in flags, and the operation would block.

EBADF fd either not valid, or doesn't refer to a pipe.

EINVAL nr_segs is greater than IOV_MAX; or memory not aligned if SPLICE_F_GIFT set.

ENOMEM Out of memory.

VERSIONS

The vmsplice() system call first appeared in Linux 2.6.17; library support was added to glibc in version 2.5.

CONFORMING TO

This system call is Linux-specific.

NOTES

vmsplice() follows the other vectorized read/write type functions when it comes to limitations on the number of segments being passed in. This limit is IOV_MAX as defined in <limits.h>. Currently, this limit is 1024.

vmsplice() really supports true splicing only from user memory to a pipe. In the opposite direction, it actually just copies the data to userspace. But this makes the interface nice and symmetric and enables people to build on vmsplice() with room for future improvement in performance.

SEE ALSO

splice(2), tee(2), pipe(7)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

Linux

2019-03-06

VMSPLICE(2)