



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Add-Member'

PS C:\Users\wahid> Get-Help Add-Member

NAME

Add-Member

SYNOPSIS

Adds custom properties and methods to an instance of a PowerShell object.

SYNTAX

```
Add-Member [-MemberType] {AliasProperty | CodeMethod | CodeProperty |  
NoteProperty | ScriptMethod | ScriptProperty} [-Name] <System.String>  
[[-Value] <System.Object>] [[-SecondValue] <System.Object>] [-Force]  
-InputObject <System.Management.Automation.PSObject> [-PassThru] [-TypeName  
<System.String>] [<CommonParameters>]
```

```
Add-Member [-NotePropertyName] <System.String> [-NotePropertyValue]  
<System.Object> [-Force] -InputObject <System.Management.Automation.PSObject>  
[-PassThru] [-TypeName <System.String>] [<CommonParameters>]
```

```
Add-Member [-NotePropertyMembers] <System.Collections.IDictionary> [-Force]  
-InputObject <System.Management.Automation.PSObject> [-PassThru] [-TypeName  
<System.String>] [<CommonParameters>]
```

```
Add-Member -InputObject <System.Management.Automation.PSObject> [-PassThru]
[-TypeName <System.String>] [<CommonParameters>]
```

DESCRIPTION

The `Add-Member`` cmdlet lets you add members (properties and methods) to an instance of a PowerShell object. For instance, you can add a `NoteProperty` member that contains a description of the object or a `ScriptMethod` member that runs a script to change the object.

To use `Add-Member``, pipe the object to `Add-Member``, or use the `InputObject` parameter to specify the object.

The `MemberType` parameter indicates the type of member that you want to add. The `Name` parameter assigns a name to the new member, and the `Value` parameter sets the value of the member.

The properties and methods that you add are added only to the particular instance of the object that you specify. `Add-Member`` doesn't change the object type. To create a new object type, use the `Add-Type`` cmdlet.

You can also use the `Export-Clixml`` cmdlet to save the instance of the object, including the additional members, in a file. Then you can use the `Import-Clixml`` cmdlet to re-create the instance of the object from the information that's stored in the exported file.

Beginning in Windows PowerShell 3.0, `Add-Member`` has new features that make it easier to add note properties to objects. You can use the `NotePropertyName` and `NotePropertyValue` parameters to define a note property or use the `NotePropertyMembers` parameter, which takes a hash table of note property names and values.

Also, beginning in Windows PowerShell 3.0, the PassThru parameter, which generates an output object, is needed less frequently. `Add-Member` now adds the new members directly to the input object of more types. For more information, see the PassThru parameter description.

PARAMETERS

`-Force <System.Management.Automation.SwitchParameter>`

By default, `Add-Member` can't add a new member if the object already has a member with the same. When you use the Force parameter, `Add-Member` replaces the existing member with the new member. You can't use the Force parameter to replace a standard member of a type.

`-InputObject <System.Management.Automation.PSObject>`

Specifies the object to which the new member is added. Enter a variable that contains the objects, or type a command or expression that gets the objects.

`-MemberType <System.Management.Automation.PSMemberTypes>`

Specifies the type of the member to add. This parameter is required. The acceptable values for this parameter are:

- AliasProperty

- CodeMethod

- CodeProperty

- NoteProperty

- ScriptMethod

- ScriptProperty

For information about these values, see [PSMemberTypes Enumeration](#) (xref:System.Management.Automation.PSMemberTypes) in the PowerShell SDK.

Not all objects have every type of member. If you specify a member type that the object doesn't have, PowerShell returns an error.

-Name <System.String>

Specifies the name of the member that this cmdlet adds.

-NotePropertyMembers <System.Collections.IDictionary>

Specifies a hashtable or ordered dictionary that contains key-value pair representing NoteProperty names and their values. For more information about hash tables and ordered dictionaries in PowerShell, see [about_Hash_Tables](#) (../Microsoft.PowerShell.Core/About/about_Hash_Tables.md).

This parameter was introduced in Windows PowerShell 3.0.

-NotePropertyName <System.String>

Specifies the note property name.

Use this parameter with the NotePropertyValue parameter. This parameter is optional.

This parameter was introduced in Windows PowerShell 3.0.

-NotePropertyValue <System.Object>

Specifies the note property value.

Use this parameter with the NotePropertyName parameter. This parameter is optional.

This parameter was introduced in Windows PowerShell 3.0.

`-PassThru <System.Management.Automation.SwitchParameter>`

Returns an object representing the item with which you are working. By default, this cmdlet doesn't generate any output.

For most objects, ``Add-Member`` adds the new members to the input object. However, when the input object is a string, ``Add-Member`` can't add the member to the input object. For these objects, use the `PassThru` parameter to create an output object.

In Windows PowerShell 2.0, ``Add-Member`` added members only to the `PSObject` wrapper of objects, not to the object. Use the `PassThru` parameter to create an output object for any object that has a `PSObject` wrapper.

`-SecondValue <System.Object>`

Specifies optional additional information about `AliasProperty` , `ScriptProperty` , or `CodeProperty` members.

If used when adding an `AliasProperty` , this parameter must be a data type. A conversion to the specified data type is added to the value of the `AliasProperty` . For example, if you add an `AliasProperty` that provides an alternate name for a string property, you can also specify a `SecondValue` parameter of `System.Int32` to indicate that the value of that string property should be converted to an integer when accessed using the corresponding `AliasProperty` .

For a `CodeProperty` , the value must be a reference to a method that implements a `Set` accessor. Use the ``GetMethod()`` method of a type reference to get a reference to a method. The method must take a single parameter that's a `PSObject` . The `Get` accessor is assigned using the `Value` parameter.

For a `ScriptProperty` , the value must be a script block that implements a `Set` accessor. The `Get` accessor is assigned using the `Value` parameter.

`-TypeName <System.String>`

Specifies a name for the type.

When the type is a class in the `System` namespace or a type that has a type accelerator, you can enter the short name of the type. Otherwise, the full type name is required. This parameter is effective only when the `InputObject` is a `PSObject` .

This parameter was introduced in Windows PowerShell 3.0.

`-Value <System.Object>`

Specifies the initial value of the added member. If you add an `AliasProperty` , `CodeProperty` , or `ScriptProperty` member, you can supply additional information using the `SecondValue` parameter.

- For an `AliasProperty` , the value must be the name of the property being aliased. - For a `CodeMethod` , the value must be a reference to a method. Use the ``GetMethod()`` method of a type reference to get a reference to a method. - For a `CodeProperty` , the value must be a reference to a method that implements a `Get` accessor. Use the ``GetMethod()`` method of a type reference to get a reference to a method. reference. The method must take a single parameter that's a `PSObject` . The `Set` accessor is assigned using the `SecondValue` parameter. - For a `ScriptMethod` , the value must be a script block. - For a `ScriptProperty` , the value must be a script block that implements a `Get` accessor. The `Set` accessor is assigned using the `SecondValue` parameter.

`<CommonParameters>`

This cmdlet supports the common parameters: `Verbose`, `Debug`,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

----- Example 1: Add a note property to a PSObject -----

```
$A = Get-ChildItem c:\ps-test\test.txt  
$A | Add-Member -NotePropertyName Status -NotePropertyValue Done  
$A.Status
```

Done

----- Example 2: Add an alias property to a PSObject -----

```
$A = Get-ChildItem C:\Temp\test.txt  
$A | Add-Member -MemberType AliasProperty -Name Size -Value Length  
$A.Size
```

2394

----- Example 3: Add a StringUse note property to a string -----

```
$A = "A string"  
$A = $A | Add-Member -NotePropertyMembers @{StringUse="Display"} -PassThru  
$A.StringUse
```

Display

----- Example 4: Add a script method to a FileInfo object -----

```

$A = Get-ChildItem C:\Temp\test.txt
$S = {[math]::Round(($this.Length / 1MB), 2)}
$A | Add-Member -MemberType ScriptMethod -Name "SizeInMB" -Value $S
$A.SizeInMB()

```

0.43

----- Example 5: Create a custom object -----

```

$Asset = New-Object -TypeName PSObject
$Asset | Add-Member -NotePropertyMembers @{Name="Server30"} -TypeName Asset
$Asset | Add-Member -NotePropertyMembers @{System="Server Core"}
$Asset | Add-Member -NotePropertyMembers @{PSVersion="4.0"}
$Asset | Get-Member -MemberType Properties

```

TypeName: Asset

Name	MemberType	Definition
Name	NoteProperty	string Name=Server30
PSVersion	NoteProperty	string PSVersion=4.0
System	NoteProperty	string System=Server Core

```

$Asset.PSObject.Properties | Format-Table Name, MemberType, TypeNameOfValue,
Value

```

Name	MemberType	TypeNameOfValue	Value
Name	NoteProperty	System.String	Server30
System	NoteProperty	System.String	Server Core
PSVersion	NoteProperty	System.String	4.0

Inspecting the raw list of properties shows the properties in the order that they were added to the object. `Format-Table` is used in this example to create output similar to `Get-Member`.

----- Example 6: Add an AliasProperty to an object -----

```
PS> $obj = [pscustomobject]@{  
    Name = 'Doris'  
    Age = '20'  
}
```

```
PS> $obj | Add-Member -MemberType AliasProperty -Name 'intAge' -Value age  
-SecondValue uint32
```

```
PS> $obj | Get-Member
```

```
TypeName: System.Management.Automation.PSCustomObject
```

Name	MemberType	Definition
intAge	AliasProperty	intAge = (System.UInt32)age
Equals	Method	bool Equals(System.Object obj)
GetHashCode	Method	int GetHashCode()
GetType	Method	type GetType()
ToString	Method	string ToString()
Age	NoteProperty	string Age=20
Name	NoteProperty	string Name=Doris

```
PS> $obj
```

```
Name : Doris  
Age : 20  
intAge : 20
```

```
PS> $obj.Age + 1
```

201

```
PS> $obj.intAge + 1
```

21

The intAge property is an AliasProperty for the Age property, but the type is guaranteed to be uint32 .

---- Example 7: Add get and set methods to a custom object ----

```
$user = [pscustomobject]@{
    Name     = 'User1'
    Age      = 29
    StartDate = [datetime]'2019-05-05'
    Position = [pscustomobject]@{
        DepartmentName = 'IT'
        Role = 'Manager'
    }
}

$addMemberSplat = @{
    MemberType = 'ScriptProperty'
    Name = 'Title'
    Value = { $this.Position.Role }          # getter
    SecondValue = { $this.Position.Role = $args[0] } # setter
}

$user | Add-Member @addMemberSplat
$user | Get-Member
```

TypeName: System.Management.Automation.PSCustomObject

Name	MemberType	Definition
------	------------	------------

Equals	Method	bool Equals(System.Object obj)
--------	--------	--------------------------------

```
GetHashCode Method    int GetHashCode()
GetType    Method    type GetType()
ToString   Method    string ToString()
Age        NoteProperty int Age=29
Name       NoteProperty string Name=User1
Position   NoteProperty System.Management.Automation.PSCustomObject
Position=@{DepartmentName=IT; Role=Manager}
StartDate  NoteProperty datetime StartDate=5/5/2019 12:00:00 AM
Title      ScriptProperty System.Object Title {get= $this.Position.Role ;set=
$this.Position.Role = $args[0] ;}

$user.Title = 'Dev Manager'
```

```
Name      : User1
Age       : 29
StartDate : 5/5/2019 12:00:00 AM
Position  : @{DepartmentName=IT; Role=Dev Manager}
Title     : Dev Manager
```

Notice that the Title property is a ScriptProperty that has a Get and Set method. When we assign a new value to the Title property, the Set method is called and changes the value of the Role property in the Position property.

REMARKS

To see the examples, type: "get-help Add-Member -examples".

For more information, type: "get-help Add-Member -detailed".

For technical information, type: "get-help Add-Member -full".

For online help, type: "get-help Add-Member -online"