

Full credit is given to the above companies including the OS that this PDF file was generated!

# Red Hat Enterprise Linux Release 9.2 Manual Pages on 'LIST\_HEAD\_INITIALIZER.3' command

Red Hal Enterprise Linux Release 9.2 Manual Pages On LIST_HEAD_					
\$ man LIST_H	EAD_INITIALIZER.3				
LIST(3)	Linux Programm	er's Manual	LIST(3)		
NAME					
LIST_EMF	PTY, LIST_ENTRY,	LIST_FIRST,	LIST_FOREACH,	LIST_HEAD,	
LIST_HEAD_INITIALIZER, LIST_INIT, LIST_INSERT_AFTER, LIST_INSERT_BE?					
FORE, LIST_INSERT_HEAD, LIST_NEXT, LIST_REMOVE - implementation of a					
doubly link	ed list				
SYNOPSIS					
#include <sys queue.h=""></sys>					
int LIST_EMPTY(LIST_HEAD *head);					
LIST_ENT	LIST_ENTRY(TYPE);				
struct TYP	struct TYPE *LIST_FIRST(LIST_HEAD *head);				
LIST_FOR	LIST_FOREACH(struct TYPE *var, LIST_HEAD *head, LIST_ENTRY NAME);				
LIST_HEA	LIST_HEAD(HEADNAME, TYPE);				
LIST_HEA	LIST_HEAD LIST_HEAD_INITIALIZER(LIST_HEAD head);				
void LIST_	void LIST_INIT(LIST_HEAD *head);				
void LIST_INSERT_AFTER(struct TYPE *listelm, struct TYPE *elm,					
1	LIST_ENTRY NAME);				

void LIST\_INSERT\_BEFORE(struct TYPE \*listelm, struct TYPE \*elm,

LIST\_ENTRY NAME);

void LIST\_INSERT\_HEAD(LIST\_HEAD \*head, struct TYPE \*elm,

LIST\_ENTRY NAME);

struct TYPE \*LIST\_NEXT(struct TYPE \*elm, LIST\_ENTRY NAME);

void LIST\_REMOVE(struct TYPE \*elm, LIST\_ENTRY NAME);

#### DESCRIPTION

These macros define and operate on doubly linked lists. In the macro definitions, TYPE is the name of a user-defined structure, that must contain a field of type LIST\_ENTRY, named NAME. The argument HEADNAME is the name of a user-defined structure that must be declared using the macro LIST\_HEAD().

A list is headed by a structure defined by the LIST\_HEAD() macro. This structure contains a single pointer to the first element on the list. The elements are doubly linked so that an arbitrary element can be re? moved without traversing the list. New elements can be added to the list after an existing element, before an existing element, or at the head of the list. A LIST\_HEAD structure is declared as follows:

LIST\_HEAD(HEADNAME, TYPE) head;

where struct HEADNAME is the structure to be defined, and struct TYPE

is the type of the elements to be linked into the list. A pointer to

the head of the list can later be declared as:

struct HEADNAME \*headp;

(The names head and headp are user selectable.)

The macro LIST\_HEAD\_INITIALIZER() evaluates to an initializer for the list head.

The macro LIST\_EMPTY() evaluates to true if there are no elements in the list.

The macro LIST\_ENTRY() declares a structure that connects the elements in the list.

The macro LIST\_FIRST() returns the first element in the list or NULL if

the list is empty.

The macro LIST\_FOREACH() traverses the list referenced by head in the

forward direction, assigning each element in turn to var.

The macro LIST\_INIT() initializes the list referenced by head.

The macro LIST\_INSERT\_HEAD() inserts the new element elm at the head of the list.

The macro LIST\_INSERT\_AFTER() inserts the new element elm after the el?

ement listelm.

The macro LIST\_INSERT\_BEFORE() inserts the new element elm before the element listelm.

The macro LIST\_NEXT() returns the next element in the list, or NULL if this is the last.

The macro LIST\_REMOVE() removes the element elm from the list.

## **RETURN VALUE**

LIST\_EMPTY() returns nonzero if the list is empty, and zero if the list contains at least one entry.

LIST FIRST(), and LIST NEXT() return a pointer to the first or next

TYPE structure, respectively.

LIST\_HEAD\_INITIALIZER() returns an initializer that can be assigned to

the list head.

### CONFORMING TO

Not in POSIX.1, POSIX.1-2001 or POSIX.1-2008. Present on the BSDs

(LIST macros first appeared in 4.4BSD).

### BUGS

The macro LIST\_FOREACH() doesn't allow var to be removed or freed within the loop, as it would interfere with the traversal. The macro LIST\_FOREACH\_SAFE(), which is present on the BSDs but is not present in glibc, fixes this limitation by allowing var to safely be removed from the list and freed from within the loop without interfering with the traversal.

#### EXAMPLES

#include <stddef.h>
#include <stdio.h>
#include <stdlib.h>
#include <stdlib.h>
struct entry {
 int data;
 LIST\_ENTRY(entry) entries; /\* List. \*/
};
LIST\_HEAD(listhead, entry);

```
main(void)
```

```
{
```

```
struct entry *n1, *n2, *n3, *np;
struct listhead head;
                               /* List head. */
int i;
LIST_INIT(&head);
                                /* Initialize the list. */
n1 = malloc(sizeof(struct entry)); /* Insert at the head. */
LIST_INSERT_HEAD(&head, n1, entries);
n2 = malloc(sizeof(struct entry)); /* Insert after. */
LIST_INSERT_AFTER(n1, n2, entries);
n3 = malloc(sizeof(struct entry)); /* Insert before. */
LIST_INSERT_BEFORE(n2, n3, entries);
i = 0;
                         /* Forward traversal. */
LIST_FOREACH(np, &head, entries)
  np->data = i++;
LIST_REMOVE(n2, entries); /* Deletion. */
free(n2);
                        /* Forward traversal. */
LIST_FOREACH(np, &head, entries)
  printf("%i\n", np->data);
                        /* List Deletion. */
n1 = LIST_FIRST(&head);
while (n1 != NULL) {
  n2 = LIST_NEXT(n1, entries);
  free(n1);
  n1 = n2;
}
LIST_INIT(&head);
exit(EXIT_SUCCESS);
```

```
}
```

SEE ALSO

insque(3), queue(7)

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

GNU 2020-12-21 LIST(3)