



## ***Red Hat Enterprise Linux Release 9.2 Manual Pages on 'login.1' command***

***\$ man login.1***

LOGIN(1)                    User Commands                    LOGIN(1)

NAME

login - begin session on the system

SYNOPSIS

login [-p] [-h host] [-H] [-f username|username]

DESCRIPTION

login is used when signing onto a system. If no argument is given, login prompts for the username.

The user is then prompted for a password, where appropriate. Echoing is disabled to prevent revealing the password. Only a number of password failures are permitted before login exits and the communications link is severed. See LOGIN\_RETRIES in CONFIG FILE ITEMS section.

If password aging has been enabled for the account, the user may be prompted for a new password before proceeding. In such case old password must be provided and the new password entered before continuing. Please refer to passwd(1) for more information.

The user and group ID will be set according to their values in the /etc/passwd file. There is one exception if the user ID is zero. In this case, only the primary group ID of the account is set. This should allow the system administrator to login even in case of network problems. The environment variable values for \$HOME, \$USER, \$SHELL, \$PATH, \$LOGNAME, and \$MAIL are set according to the appropriate fields in the password entry. \$PATH defaults to /usr/local/bin:/bin:/usr/bin

for normal users, and to

/usr/local/sbin:/usr/local/bin:/sbin:/bin:/usr/sbin:/usr/bin for root,

if not otherwise configured.

The environment variable \$TERM will be preserved, if it exists, else it will be initialized to the terminal type on your tty. Other environment variables are preserved if the -p option is given.

Then the user's shell is started. If no shell is specified for the user in /etc/passwd, then /bin/sh is used. If there is no home directory specified in /etc/passwd, then / is used, followed by .hushlogin check as described below.

If the file .hushlogin exists, then a "quiet" login is performed. This disables the checking of mail and the printing of the last login time and message of the day. Otherwise, if /var/log/lastlog exists, the last login time is printed, and the current login is recorded.

## OPTIONS

-p

Used by getty(8) to tell login to preserve the environment.

-f

Used to skip a login authentication. This option is usually used by the getty(8) autologin feature.

-h

Used by other servers (such as telnetd(8)) to pass the name of the remote host to login so that it can be placed in utmp and wtmp.

Only the superuser is allowed use this option.

Note that the -h option has an impact on the PAM service name. The standard service name is login, but with the -h option, the name is remote. It is necessary to create proper PAM config files (for example, /etc/pam.d/login and /etc/pam.d/remote).

-H

Used by other servers (for example, telnetd(8)) to tell login that printing the hostname should be suppressed in the login: prompt.

See also LOGIN\_PLAIN\_PROMPT below.

--help

Display help text and exit.

`-V, --version`

Display version information and exit.

## CONFIG FILE ITEMS

login reads the `/etc/login.defs` configuration file (see `login.defs(5)`).

Note that the configuration file could be distributed with another package (usually `shadow-utils`). The following configuration items are relevant for login:

**MOTD\_FILE** (string)

Specifies a ":" delimited list of "message of the day" files and directories to be displayed upon login. If the specified path is a directory then displays all files with `.motd` file extension in version-sort order from the directory.

The default value is `/usr/share/misc/motd:/run/motd:/etc/motd`. If the **MOTD\_FILE** item is empty or a quiet login is enabled, then the message of the day is not displayed. Note that the same functionality is also provided by the `pam_motd(8)` PAM module.

The directories in the **MOTD\_FILE** are supported since version 2.36.

Note that login does not implement any filenames overriding behavior like `pam_motd` (see also **MOTD\_FIRSTONLY**), but all content from all files is displayed. It is recommended to keep extra logic in content generators and use `/run/motd.d` rather than rely on overriding behavior hardcoded in system tools.

**MOTD\_FIRSTONLY** (boolean)

Forces login to stop display content specified by **MOTD\_FILE** after the first accessible item in the list. Note that a directory is one item in this case. This option allows login semantics to be configured to be more compatible with `pam_motd`. The default value is `no`.

**LOGIN\_PLAIN\_PROMPT** (boolean)

Tell login that printing the hostname should be suppressed in the `login: prompt`. This is an alternative to the `-H` command line option. The default value is `no`.

LOGIN\_TIMEOUT (number)

Maximum time in seconds for login. The default value is 60.

LOGIN\_RETRIES (number)

Maximum number of login retries in case of a bad password. The default value is 3.

LOGIN\_KEEP\_USERNAME (boolean)

Tell login to only re-prompt for the password if authentication failed, but the username is valid. The default value is no.

FAIL\_DELAY (number)

Delay in seconds before being allowed another three tries after a login failure. The default value is 5.

TTYPERM (string)

The terminal permissions. The default value is 0600 or 0620 if tty group is used.

TTYGROUP (string)

The login tty will be owned by the TTYGROUP. The default value is tty. If the TTYGROUP does not exist, then the ownership of the terminal is set to the user's primary group.

The TTYGROUP can be either the name of a group or a numeric group identifier.

HUSHLOGIN\_FILE (string)

If defined, this file can inhibit all the usual chatter during the login sequence. If a full pathname (for example, /etc/hushlogins) is specified, then hushed mode will be enabled if the user's name or shell are found in the file. If this global hush login file is empty then the hushed mode will be enabled for all users.

If a full pathname is not specified, then hushed mode will be enabled if the file exists in the user's home directory.

The default is to check /etc/hushlogins and if it does not exist then ~/.hushlogin.

If the HUSHLOGIN\_FILE item is empty, then all the checks are disabled.

DEFAULT\_HOME (boolean)

Indicate if login is allowed if we cannot change directory to the home directory. If set to yes, the user will login in the root (/) directory if it is not possible to change directory to their home.

The default value is yes.

LASTLOG\_UID\_MAX (unsigned number)

Highest user ID number for which the lastlog entries should be updated. As higher user IDs are usually tracked by remote user identity and authentication services there is no need to create a huge sparse lastlog file for them. No LASTLOG\_UID\_MAX option present in the configuration means that there is no user ID limit for writing lastlog entries. The default value is ULONG\_MAX.

LOG\_UNKFAIL\_ENAB (boolean)

Enable display of unknown usernames when login failures are recorded. The default value is no.

Note that logging unknown usernames may be a security issue if a user enters their password instead of their login name.

ENV\_PATH (string)

If set, it will be used to define the PATH environment variable when a regular user logs in. The default value is /usr/local/bin:/bin:/usr/bin.

ENV\_ROOTPATH (string), ENV\_SUPATH (string)

If set, it will be used to define the PATH environment variable when the superuser logs in. ENV\_ROOTPATH takes precedence. The default value is

/usr/local/sbin:/usr/local/bin:/sbin:/bin:/usr/sbin:/usr/bin.

## FILES

/var/run/utmp, /var/log/wtmp, /var/log/lastlog, /var/spool/mail/\*,  
/etc/motd, /etc/passwd, /etc/nologin, /etc/pam.d/login,  
/etc/pam.d/remote, /etc/hushlogins, \$HOME/.hushlogin

## BUGS

The undocumented BSD -r option is not supported. This may be required by some rlogind(8) programs.

A recursive login, as used to be possible in the good old days, no

longer works; for most purposes su(1) is a satisfactory substitute. Indeed, for security reasons, login does a vhangup(2) system call to remove any possible listening processes on the tty. This is to avoid password sniffing. If one uses the command login, then the surrounding shell gets killed by vhangup(2) because it's no longer the true owner of the tty. This can be avoided by using exec login in a top-level shell or xterm.

## AUTHORS

Derived from BSD login 5.40 (5/9/89) by Michael Glad <glad@daimi.dk> for HP-UX. Ported to Linux 0.12: Peter Orbaek <poe@daimi.aau.dk>. Rewritten to a PAM-only version by Karel Zak <kzak@redhat.com>

## SEE ALSO

mail(1), passwd(1), passwd(5), utmp(5), environ(7), getty(8), init(8), lastlog(8), shutdown(8)

## REPORTING BUGS

For bug reports, use the issue tracker at <https://github.com/karelzak/util-linux/issues>.

## AVAILABILITY

The login command is part of the util-linux package which can be downloaded from Linux Kernel Archive <<https://www.kernel.org/pub/linux/utils/util-linux/>>.

util-linux 2.37.4

2022-02-14

LOGIN(1)