



Red Hat Enterprise Linux Release 9.2 Manual Pages on 'vgimportdevices.8' command

\$ man vgimportdevices.8

VGIMPORTDEVICES(8) System Manager's Manual VGIMPORTDEVICES(8)

NAME

vgimportdevices ? Add devices for a VG to the devices file.

SYNOPSIS

vgimportdevices option_args position_args

[option_args]

DESCRIPTION

vgimportdevices adds PVs from a VG to the devices file. This is similar to using using lvmdevices --adddev to add each PV to the devices file individually. vgimportdevices will also update the VG metadata to include the device IDs of each PV. vgimportdevices will create a new devices file if none exists.

When a devices file is used, the regex filter is ignored, except in the case of vgimportdevices which will apply the regex filter when looking for the VGs to import to the devices file. Use vgimportdevices -a to import all VGs on a system to the devices file.

USAGE

Add devices from specific VGs to the devices file.

vgimportdevices VG|Tag|Select ...

[-S|--select String]

[COMMON_OPTIONS]

Add devices from all accessible VGs to the devices file.

vgimportdevices -a|--all

[COMMON_OPTIONS]

Common options for command:

[--foreign]

[--reportformat basic|json|json_std]

Common options for lvm:

[-d|--debug]

[-h|--help]

[-q|--quiet]

[-t|--test]

[-v|--verbose]

[-y|--yes]

[--commandprofile String]

[--config String]

[--devices PV]

[--devicesfile String]

[--driverloaded y|n]

[--journal String]

[--lockopt String]

[--longhelp]

[--nohints]

[--nolocking]

[--profile String]

[--version]

OPTIONS

-a|--all

--commandprofile String

The command profile to use for command configuration. See `lvm.conf(5)` for more information about profiles.

--config String

Config settings for the command. These override `lvm.conf(5)` settings. The String arg uses the same format as `lvm.conf(5)`, or may use section/field syntax. See `lvm.conf(5)` for more information about config.

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

--devices PV

Restricts the devices that are visible and accessible to the command. Devices not listed will appear to be missing. This option can be repeated, or accepts a comma separated list of devices. This overrides the devices file.

--devicesfile String

A file listing devices that LVM should use. The file must exist in /etc/lvm/devices/ and is managed with the lvmdevices(8) command. This overrides the lvm.conf(5) devices/devicesfile and devices/use_devicesfile settings.

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper. For testing and debugging.

--foreign

Report/display foreign VGs that would otherwise be skipped. See lvmsystemid(7) for more information about foreign VGs.

-h|--help

Display help text.

--journal String

Record information in the systemd journal. This information is in addition to information enabled by the lvm.conf log/journal setting. command: record information about the command. output: record the default command output. debug: record full command debugging.

--lockopt String

Used to pass options for special cases to lvmlockd. See lvmlockd(8) for more information.

--longhelp

Display long help text.

--nohints

Do not use the hints file to locate devices for PVs. A command may read more devices to find PVs when hints are not used. The command will still perform standard hint file invalidation where appropriate.

`--nolocking`

Disable locking. Use with caution, concurrent commands may produce incorrect results.

`--profile String`

An alias for `--commandprofile` or `--metadataprofile`, depending on the command.

`-q|--quiet ...`

Suppress output and log messages. Overrides `--debug` and `--verbose`. Repeat once to also suppress any prompts with answer 'no'.

`--reportformat basic|json|json_std`

Overrides current output format for reports which is defined globally by the `report/output_format` setting in `lvm.conf(5)`. `basic` is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. `json` produces report output in JSON format. `json_std` produces report output in JSON format which is more compliant with JSON standard. See `lvmreport(7)` for more information.

`-S|--select String`

Select objects for processing and reporting based on specified criteria. The criteria syntax is described by `--select help` and `lvmreport(7)`. For reporting commands, one row is displayed for each object matching the criteria. See `--options help` for selectable object fields. Rows can be displayed with an additional "selected" field (`-o selected`) showing 1 if the row matches the selection and 0 otherwise. For non-reporting commands which process LVM entities, the selection is used to choose items to process.

-t|--test

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies on reading back metadata it believes has changed but hasn't.

-v|--verbose ...

Set verbose level. Repeat from 1 to 4 times to increase the default tail of messages sent to stdout and stderr.

--version

Display version information.

-y|--yes

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see -qq.)

VARIABLES

VG Volume Group name. See lvm(8) for valid names.

Tag Tag name. See lvm(8) for information about tag names and using tags in place of a VG, LV or PV.

Select Select indicates that a required positional parameter can be omitted if the --select option is used. No arg appears in this position.

String See the option description for information about the string content.

Size[UNIT]

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT. UNIT represents other possible input units: b|B is bytes, s|S is sectors of 512 bytes, k|K is KiB, m|M is MiB, g|G is GiB, t|T is TiB, p|P is PiB, e|E is EiB. (This should not be confused with the output control --units, where capital letters mean multiple of

1000.)

ENVIRONMENT VARIABLES

See [lvm\(8\)](#) for information about environment variables used by lvm.

For example, `LVM_VG_NAME` can generally be substituted for a required VG parameter.

SEE ALSO

[lvm\(8\)](#), [lvm.conf\(5\)](#), [lvmconfig\(8\)](#), [lvmdevices\(8\)](#),
[pvchange\(8\)](#), [pvck\(8\)](#), [pvcreate\(8\)](#), [pvdisplay\(8\)](#), [pvmove\(8\)](#),
[pvremove\(8\)](#), [pvresize\(8\)](#), [pvs\(8\)](#), [pvscan\(8\)](#),
[vgcfgbackup\(8\)](#), [vgcfgrestore\(8\)](#), [vgchange\(8\)](#), [vgck\(8\)](#), [vgcreate\(8\)](#),
[vgconvert\(8\)](#), [vgdisplay\(8\)](#), [vgexport\(8\)](#), [vgextend\(8\)](#), [vgimport\(8\)](#),
[vgimportclone\(8\)](#), [vgimportdevices\(8\)](#), [vgmerge\(8\)](#), [vgmknodes\(8\)](#),
[vgreduce\(8\)](#), [vgremove\(8\)](#), [vgrename\(8\)](#), [vgs\(8\)](#), [vgscan\(8\)](#), [vgsplit\(8\)](#),
[lvcreate\(8\)](#), [lvchange\(8\)](#), [lvconvert\(8\)](#), [lvdisplay\(8\)](#), [lvextend\(8\)](#),
[lvreduce\(8\)](#), [lvremove\(8\)](#), [lvrename\(8\)](#), [lvresize\(8\)](#), [lvs\(8\)](#), [lvscan\(8\)](#),
[lvm-fullreport\(8\)](#), [lvm-lvpoll\(8\)](#), [blkdeactivate\(8\)](#), [lvmdump\(8\)](#),
[dmeventd\(8\)](#), [lvmpolld\(8\)](#), [lvmlockd\(8\)](#), [lvmlockctl\(8\)](#), [cmirror\(8\)](#),
[lvmdbusd\(8\)](#), [fsadm\(8\)](#),
[lvmsystemid\(7\)](#), [lvmreport\(7\)](#), [lvraid\(7\)](#), [lvthin\(7\)](#), [lvmcache\(7\)](#)

Red Hat, Inc. LVM TOOLS 2.03.17(2) (2022-11-10) [VGIMPORTDEVICES\(8\)](#)