



Rocky Enterprise Linux 9.2 Manual Pages on command 'lvremove.8'

\$ man lvremove.8

LVREMOVE(8) System Manager's Manual LVREMOVE(8)

NAME

lvremove ? Remove logical volume(s) from the system

SYNOPSIS

lvremove position_args

[option_args]

DESCRIPTION

lvremove removes one or more LVs. For standard LVs, this returns the logical extents that were used by the LV to the VG for use by other LVs.

Confirmation will be requested before deactivating any active LV prior to removal. LVs cannot be deactivated or removed while they are open (e.g. if they contain a mounted filesystem). Removing an origin LV will also remove all dependent snapshots.

When a single force option is used, LVs are removed without confirmation, and the command will try to deactivate unused LVs.

To remove damaged LVs, two force options may be required (-ff).

Historical LVs

If the configuration setting `metadata/record_lvs_history` is enabled and the LV being removed forms part of the history of at least one LV that is still present, then a simplified representation of the LV will be retained. This includes the time of removal (`lv_time_removed` reporting field), creation time (`lv_time`), name (`lv_name`), LV uuid (`lv_uuid`) and VG name (`vg_name`). This allows later reporting to see the ancestry chain of thin snapshot volumes, even after some intermediate LVs have been removed. The names of such historical LVs acquire a hyphen as a prefix (e.g. '-lvol1') and cannot be reactivated. Use `lvremove` a second time, with the hyphen, to remove the record of the former LV completely.

USAGE

`lvremove VG|LV|Tag|Select ...`

[`-A|--autobackup y|n`]

[`-f|--force`]

[`-S|--select String`]

[`--nohistory`]

[`--noudevsync`]

[`--reportformat basic|json|json_std`]

[`COMMON_OPTIONS`]

Common options for `lvm`:

[`-d|--debug`]

[`-h|--help`]

[`-q|--quiet`]

[`-t|--test`]

[`-v|--verbose`]

[`-y|--yes`]

[`--commandprofile String`]

[`--config String`]

[`--devices PV`]

[`--devicesfile String`]

[`--driverloaded y|n`]

[`--journal String`]

[--lockopt String]

[--longhelp]

[--nohints]

[--nolocking]

[--profile String]

[--version]

OPTIONS

-A|--autobackup y|n

Specifies if metadata should be backed up automatically after a change. Enabling this is strongly advised! See `vgcfgbackup(8)` for more information.

--commandprofile String

The command profile to use for command configuration. See `lvm.conf(5)` for more information about profiles.

--config String

Config settings for the command. These override `lvm.conf(5)` settings. The String arg uses the same format as `lvm.conf(5)`, or may use section/field syntax. See `lvm.conf(5)` for more information about config.

-d|--debug ...

Set debug level. Repeat from 1 to 6 times to increase the detail of messages sent to the log file and/or syslog (if configured).

--devices PV

Restricts the devices that are visible and accessible to the command. Devices not listed will appear to be missing. This option can be repeated, or accepts a comma separated list of devices. This overrides the devices file.

--devicesfile String

A file listing devices that LVM should use. The file must exist in `/etc/lvm/devices/` and is managed with the `lvmdevices(8)` command. This overrides the `lvm.conf(5)` `devices/devicesfile` and `devices/use_devicesfile` settings.

--driverloaded y|n

If set to no, the command will not attempt to use device-mapper.

For testing and debugging.

-f|--force ...

Override various checks, confirmations and protections. Use with extreme caution.

-h|--help

Display help text.

--journal String

Record information in the systemd journal. This information is in addition to information enabled by the lvm.conf log/journal setting. command: record information about the command. out? put: record the default command output. debug: record full command debugging.

--lockopt String

Used to pass options for special cases to lvmlockd. See lvmlockd(8) for more information.

--longhelp

Display long help text.

--nohints

Do not use the hints file to locate devices for PVs. A command may read more devices to find PVs when hints are not used. The command will still perform standard hint file invalidation where appropriate.

--nohistory

Do not record history of LVs being removed. This has no effect unless the configuration setting metadata/record_lvs_history is enabled.

--nolocking

Disable locking. Use with caution, concurrent commands may produce incorrect results.

--noudevsync

Disables udev synchronisation. The process will not wait for notification from udev. It will continue irrespective of any

sible udev processing in the background. Only use this if udev is not running or has rules that ignore the devices LVM creates.

`--profile String`

An alias for `--commandprofile` or `--metadataprofile`, depending on the command.

`-q|--quiet ...`

Suppress output and log messages. Overrides `--debug` and `--verbose`. Repeat once to also suppress any prompts with answer 'no'.

`--reportformat basic|json|json_std`

Overrides current output format for reports which is defined globally by the `report/output_format` setting in `lvm.conf(5)`. `basic` is the original format with columns and rows. If there is more than one report per command, each report is prefixed with the report name for identification. `json` produces report output in JSON format. `json_std` produces report output in JSON format which is more compliant with JSON standard. See `lvmreport(7)` for more information.

`-S|--select String`

Select objects for processing and reporting based on specified criteria. The criteria syntax is described by `--select help` and `lvmreport(7)`. For reporting commands, one row is displayed for each object matching the criteria. See `--options help` for selectable object fields. Rows can be displayed with an additional "selected" field (`-o selected`) showing 1 if the row matches the selection and 0 otherwise. For non-reporting commands which process LVM entities, the selection is used to choose items to process.

`-t|--test`

Run in test mode. Commands will not update metadata. This is implemented by disabling all metadata writing but nevertheless returning success to the calling function. This may lead to unusual error messages in multi-stage operations if a tool relies

on reading back metadata it believes has changed but hasn't.

`-v|--verbose ...`

Set verbose level. Repeat from 1 to 4 times to increase the de? tail of messages sent to stdout and stderr.

`--version`

Display version information.

`-y|--yes`

Do not prompt for confirmation interactively but always assume the answer yes. Use with extreme caution. (For automatic no, see `-qq`.)

VARIABLES

`VG` Volume Group name. See `lvm(8)` for valid names.

`LV` Logical Volume name. See `lvm(8)` for valid names. An LV positional arg generally includes the VG name and LV name, e.g. `VG/LV`.

`Tag` Tag name. See `lvm(8)` for information about tag names and using tags in place of a VG, LV or PV.

`Select` Select indicates that a required positional parameter can be omitted if the `--select` option is used. No arg appears in this position.

`String` See the option description for information about the string content.

`Size[UNIT]`

Size is an input number that accepts an optional unit. Input units are always treated as base two values, regardless of capitalization, e.g. 'k' and 'K' both refer to 1024. The default input unit is specified by letter, followed by |UNIT. UNIT represents other possible input units: b|B is bytes, s|S is sectors of 512 bytes, k|K is KiB, m|M is MiB, g|G is GiB, t|T is TiB, p|P is PiB, e|E is EiB. (This should not be confused with the output control `--units`, where capital letters mean multiple of 1000.)

ENVIRONMENT VARIABLES

See [lvm\(8\)](#) for information about environment variables used by lvm.

For example, `LVM_VG_NAME` can generally be substituted for a required VG parameter.

EXAMPLES

Remove an active LV without asking for confirmation.

```
lvremove -f vg00/lvol1
```

Remove all LVs the specified VG.

```
lvremove vg00
```

SEE ALSO

[lvm\(8\)](#), [lvm.conf\(5\)](#), [lvmconfig\(8\)](#), [lvmdevices\(8\)](#),
[pvchange\(8\)](#), [pvck\(8\)](#), [pvcreate\(8\)](#), [pvdisplay\(8\)](#), [pvmove\(8\)](#),
[pvremove\(8\)](#), [pvresize\(8\)](#), [pvs\(8\)](#), [pvscan\(8\)](#),
[vgcfgbackup\(8\)](#), [vgcfgrestore\(8\)](#), [vgchange\(8\)](#), [vgck\(8\)](#), [vgcreate\(8\)](#),
[vgconvert\(8\)](#), [vgdisplay\(8\)](#), [vgexport\(8\)](#), [vgextend\(8\)](#), [vgimport\(8\)](#),
[vgimportclone\(8\)](#), [vgimportdevices\(8\)](#), [vgmerge\(8\)](#), [vgmknodes\(8\)](#),
[vgreduce\(8\)](#), [vgremove\(8\)](#), [vgrename\(8\)](#), [vgs\(8\)](#), [vgscan\(8\)](#), [vgsplit\(8\)](#),
[lvcreate\(8\)](#), [lvchange\(8\)](#), [lvconvert\(8\)](#), [lvdisplay\(8\)](#), [lvextend\(8\)](#),
[lvreduce\(8\)](#), [lvremove\(8\)](#), [lvrename\(8\)](#), [lvresize\(8\)](#), [lvs\(8\)](#), [lvscan\(8\)](#),
[lvm-fullreport\(8\)](#), [lvm-lvpoll\(8\)](#), [blkdeactivate\(8\)](#), [lvmdump\(8\)](#),
[dmeventd\(8\)](#), [lvmpolld\(8\)](#), [lvmlckd\(8\)](#), [lvmlckctl\(8\)](#), [cmirror\(8\)](#),
[lvmdbusd\(8\)](#), [fsadm\(8\)](#),
[lvmsystemid\(7\)](#), [lvmreport\(7\)](#), [lvraid\(7\)](#), [lvmthin\(7\)](#), [lvmdcache\(7\)](#)

Red Hat, Inc. LVM TOOLS 2.03.17(2) (2022-11-10) [LVREMOVE\(8\)](#)