



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'mke2fs.conf.5'

\$ man mke2fs.conf.5

mke2fs.conf(5) File Formats Manual mke2fs.conf(5)

NAME

mke2fs.conf - Configuration file for mke2fs

DESCRIPTION

mke2fs.conf is the configuration file for mke2fs(8). It controls the default parameters used by mke2fs(8) when it is creating ext2, ext3, or ext4 file systems.

The mke2fs.conf file uses an INI-style format. Stanzas, or top-level sections, are delimited by square braces: []. Within each section, each line defines a relation, which assigns tags to values, or to a subsection, which contains further relations or subsections. An exam?

ple of the INI-style format used by this configuration file follows be?

low:

[section1]

tag1 = value_a

tag1 = value_b

tag2 = value_c

[section 2]

```

tag3 = {
    subtag1 = subtag_value_a
    subtag1 = subtag_value_b
    subtag2 = subtag_value_c
}
tag1 = value_d
tag2 = value_e
}

```

Comments are delimited by a semicolon (;) or a hash (#) character at the beginning of the comment, and are terminated by the end of line character.

Tags and values must be quoted using double quotes if they contain spaces. Within a quoted string, the standard backslash interpretations apply: "\n" (for the newline character), "\t" (for the tab character), "\b" (for the backspace character), and "\\" (for the backslash character).

Some relations expect a boolean value. The parser is quite liberal on recognizing "yes", "y", "true", "t", "1", "on", etc. as a boolean true value, and "no", "n", "false", "nil", "0", "off" as a boolean false value.

The following stanzas are used in the mke2fs.conf file. They will be described in more detail in future sections of this document.

[options]

Contains relations which influence how mke2fs behaves.

[defaults]

Contains relations which define the default parameters used by mke2fs(8). In general, these defaults may be overridden by a definition in the fs_types stanza, or by a command-line option provided by the user.

[fs_types]

Contains relations which define defaults that should be used for specific file system and usage types. The file system type and usage type can be specified explicitly using the -t and -T options

to mke2fs(8), respectively.

[devices]

Contains relations which define defaults for specific devices.

THE [options] STANZA

The following relations are defined in the [options] stanza.

proceed_delay

If this relation is set to a positive integer, then mke2fs will wait proceed_delay seconds after asking the user for permission to proceed and then continue, even if the user has not answered the question. Defaults to 0, which means to wait until the user answers the question one way or another.

sync_kludge

If this relation is set to a positive integer, then while writing the inode table, mke2fs will request the operating system flush out pending writes to initialize the inode table every sync_kludge block groups. This is needed to work around buggy kernels that don't handle writeback throttling correctly.

THE [defaults] STANZA

The following relations are defined in the [defaults] stanza.

creator_os

This relation specifies the "creator operating system" for the file system unless it is overridden on the command line. The default value is the OS for which the mke2fs executable was compiled.

fs_type

This relation specifies the default file system type if the user does not specify it via the -t option, or if mke2fs is not started using a program name of the form mkfs.fs-type. If both the user and the mke2fs.conf file do not specify a default file system type, mke2fs will use a default file system type of ext3 if a journal was requested via a command-line option, or ext2 if not.

undo_dir

This relation specifies the directory where the undo file should be stored. It can be overridden via the `E2FSPROGS_UNDO_DIR` environment variable. If the directory location is set to the value `none`, `mke2fs` will not create an undo file.

In addition, any tags that can be specified in a per-file system tags subsection as defined below (e.g., `blocksize`, `hash_alg`, `inode_ratio`, `inode_size`, `reserved_ratio`, etc.) can also be specified in the defaults stanza to specify the default value to be used if the user does not specify one on the command line, and the file system-type specific section of the configuration file does not specify a default value.

THE [fs_types] STANZA

Each tag in the `[fs_types]` stanza names a file system type or usage type which can be specified via the `-t` or `-T` options to `mke2fs(8)`, respectively.

The `mke2fs` program constructs a list of `fs_types` by concatenating the file system type (i.e., `ext2`, `ext3`, etc.) with the usage type list.

For most configuration options, `mke2fs` will look for a subsection in the `[fs_types]` stanza corresponding with each entry in the constructed list, with later entries overriding earlier file system or usage types.

For example, consider the following `mke2fs.conf` fragment:

```
[defaults]
    base_features = sparse_super,filetype,resize_inode,dir_index
    blocksize = 4096
    inode_size = 256
    inode_ratio = 16384
```

```
[fs_types]
    ext3 = {
        features = has_journal
    }
    ext4 = {
        features = extents,flex_bg
        inode_size = 256
    }
```

```

small = {
    blocksize = 1024
    inode_ratio = 4096
}
floppy = {
    features = ^resize_inode
    blocksize = 1024
    inode_size = 128
}

```

If mke2fs started with a program name of mke2fs.ext4, then the file system type of ext4 will be used. If the file system is smaller than 3 megabytes, and no usage type is specified, then mke2fs will use a default usage type of floppy. This results in an fs_types list of "ext4, floppy". Both the ext4 subsection and the floppy subsection define an inode_size relation, but since the later entries in the fs_types list supersede earlier ones, the configuration parameter for fs_types.floppy.inode_size will be used, so the file system will have an inode size of 128.

The exception to this resolution is the features tag, which specifies a set of changes to the features used by the file system, and which is cumulative. So in the above example, first the configuration relation defaults.base_features would enable an initial feature set with the sparse_super, filetype, resize_inode, and dir_index features enabled. Then configuration relation fs_types.ext4.features would enable the extents and flex_bg features, and finally the configuration relation fs_types.floppy.features would remove the resize_inode feature, resulting in a file system feature set consisting of the sparse_super, filetype, dir_index, extents_and flex_bg features.

For each file system type, the following tags may be used in that fs_type's subsection. These tags may also be used in the default section:

base_features

This relation specifies the features which are initially enabled

for this file system type. Only one `base_features` will be used, so if there are multiple entries in the `fs_types` list whose subsections define the `base_features` relation, only the last will be used by `mke2fs(8)`.

`enable_periodic_fsck`

This boolean relation specifies whether periodic file system checks should be enforced at boot time. If set to true, checks will be forced every 180 days, or after a random number of mounts. These values may be changed later via the `-i` and `-c` command-line options to `tune2fs(8)`.

`errors` Change the behavior of the kernel code when errors are detected.

In all cases, a file system error will cause `e2fsck(8)` to check the file system on the next boot. `errors` can be one of the following:

- `continue` Continue normal execution.
- `remount-ro` Remount file system read-only.
- `panic` Cause a kernel panic.

`features`

This relation specifies a comma-separated list of features edit requests which modify the feature set used by the newly constructed file system. The syntax is the same as the `-O` command-line option to `mke2fs(8)`; that is, a feature can be prefixed by a caret (^) symbol to disable a named feature. Each feature relation specified in the `fs_types` list will be applied in the order found in the `fs_types` list.

`force_undo`

This boolean relation, if set to a value of true, forces `mke2fs` to always try to create an undo file, even if the undo file might be huge and it might extend the time to create the file system image because the inode table isn't being initialized lazily.

`default_features`

This relation specifies set of features which should be enabled

or disabled after applying the features listed in the `base_fea?` features and features relations. It may be overridden by the `-O` command-line option to `mke2fs(8)`.

`auto_64-bit_support`

This relation is a boolean which specifies whether `mke2fs(8)` should automatically add the `64bit` feature if the number of blocks for the file system requires this feature to be enabled. The `resize_inode` feature is also automatically disabled since it doesn't support 64-bit block numbers.

`default_mntopts`

This relation specifies the set of mount options which should be enabled by default. These may be changed at a later time with the `-o` command-line option to `tune2fs(8)`.

`blocksize`

This relation specifies the default blocksize if the user does not specify a blocksize on the command line.

`lazy_itable_init`

This boolean relation specifies whether the inode table should be lazily initialized. It only has meaning if the `uninit_bg` feature is enabled. If `lazy_itable_init` is true and the `uninit_bg` feature is enabled, the inode table will not be fully initialized by `mke2fs(8)`. This speeds up file system initialization noticeably, but it requires the kernel to finish initializing the file system in the background when the file system is first mounted.

`lazy_journal_init`

This boolean relation specifies whether the journal inode should be lazily initialized. It only has meaning if the `has_journal` feature is enabled. If `lazy_journal_init` is true, the journal inode will not be fully zeroed out by `mke2fs`. This speeds up file system initialization noticeably, but carries some small risk if the system crashes before the journal has been overwritten entirely one time.

journal_location

This relation specifies the location of the journal.

num_backup_sb

This relation indicates whether file systems with the sparse_super2 feature enabled should be created with 0, 1, or 2 backup superblocks.

packed_meta_blocks

This boolean relation specifies whether the allocation bitmaps, inode table, and journal should be located at the beginning of the file system.

inode_ratio

This relation specifies the default inode ratio if the user does not specify one on the command line.

inode_size

This relation specifies the default inode size if the user does not specify one on the command line.

reserved_ratio

This relation specifies the default percentage of file system blocks reserved for the super-user, if the user does not specify one on the command line.

hash_alg

This relation specifies the default hash algorithm used for the new file systems with hashed b-tree directories. Valid algorithms accepted are: legacy, half_md4, and tea.

flex_bg_size

This relation specifies the number of block groups that will be packed together to create one large virtual block group on an ext4 file system. This improves meta-data locality and performance on meta-data heavy workloads. The number of groups must be a power of 2 and may only be specified if the flex_bg file system feature is enabled.

options

This relation specifies additional extended options which should

be treated by mke2fs(8) as if they were prepended to the argument of the -E option. This can be used to configure the default extended options used by mke2fs(8) on a per-file system type basis.

discard

This boolean relation specifies whether the mke2fs(8) should attempt to discard device prior to file system creation.

cluster_size

This relation specifies the default cluster size if the bigalloc file system feature is enabled. It can be overridden via the -C command line option to mke2fs(8)

make_hugefiles

This boolean relation enables the creation of pre-allocated files as part of formatting the file system. The extent tree blocks for these pre-allocated files will be placed near the beginning of the file system, so that if all of the other metadata blocks are also configured to be placed near the beginning of the file system (by disabling the backup superblocks, using the packed_meta_blocks option, etc.), the data blocks of the pre-allocated files will be contiguous.

hugefiles_dir

This relation specifies the directory where huge files are created, relative to the file system root.

hugefiles_uid

This relation controls the user ownership for all of the files and directories created by the make_hugefiles feature.

hugefiles_gid

This relation controls the group ownership for all of the files and directories created by the make_hugefiles feature.

hugefiles_umask

This relation specifies the umask used when creating the files and directories by the make_hugefiles feature.

num_hugefiles

This relation specifies the number of huge files to be created.

If this relation is not specified, or is set to zero, and the `hugefiles_size` relation is non-zero, then `make_hugefiles` will create as many huge files as can fit to fill the entire file system.

`hugefiles_slack`

This relation specifies how much space should be reserved for other files.

`hugefiles_size`

This relation specifies the size of the huge files. If this relation is not specified, the default is to fill the entire file system.

`hugefiles_align`

This relation specifies the alignment for the start block of the huge files. It also forces the size of huge files to be a multiple of the requested alignment. If this relation is not specified, no alignment requirement will be imposed on the huge files.

`hugefiles_align_disk`

This relation specifies whether the alignment should be relative to the beginning of the hard drive (assuming that the starting offset of the partition is available to `mke2fs`). The default value is false, which will cause hugefile alignment to be relative to the beginning of the file system.

`hugefiles_name`

This relation specifies the base file name for the huge files.

`hugefiles_digits`

This relation specifies the (zero-padded) width of the field for the huge file number.

`warn_y2038_dates`

This boolean relation specifies whether `mke2fs` will issue a warning when creating a file system with 128 byte inodes (and so therefore will not support dates after January 19th, 2038). The

default value is true, except for file systems created for the GNU Hurd since it only supports 128-byte inodes.

zero_hugefiles

This boolean relation specifies whether or not zero blocks will be written to the hugefiles while `mke2fs(8)` is creating them. By default, zero blocks will be written to the huge files to avoid stale data from being made available to potentially untrusted user programs, unless the device supports a `discard/trim` operation which will take care of zeroing the device blocks. By setting `zero_hugefiles` to false, this step will always be skipped, which can be useful if it is known that the disk has been previously erased, or if the user programs that will have access to the huge files are trusted to not reveal stale data.

encoding

This relation defines the file name encoding to be used if the casefold feature is enabled. Currently the only valid encoding is `utf8-12.1` or `utf8`, which requests the most recent Unicode version; since 12.1 is the only available Unicode version, `utf8` and `utf8-12.1` have the same result. `encoding_flags` This relation defines encoding-specific flags. For `utf8` encodings, the only available flag is `strict`, which will cause attempts to create file names containing invalid Unicode characters to be rejected by the kernel. Strict mode is not enabled by default.

THE [devices] STANZA

Each tag in the [devices] stanza names device name so that per-device defaults can be specified.

fs_type

This relation specifies the default parameter for the `-t` option, if this option isn't specified on the command line.

usage_types

This relation specifies the default parameter for the `-T` option, if this option isn't specified on the command line.

`/etc/mke2fs.conf`

The configuration file for `mke2fs(8)`.

SEE ALSO

`mke2fs(8)`

E2fsprogs version 1.46.5

December 2021

`mke2fs.conf(5)`