

Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'ptsname_r.3'

\$ man ptsname_r.3

PTSNAME(3)

Linux Programmer's Manual

PTSNAME(3)

NAME

ptsname, ptsname_r - get the name of the slave pseudoterminal

SYNOPSIS

#include <stdlib.h>

char *ptsname(int fd);

int ptsname_r(int fd, char *buf, size_t buflen);

Feature Test Macro Requirements for glibc (see feature_test_macros(7)):

ptsname():

Since glibc 2.24:

_XOPEN_SOURCE >= 500 ||

(_XOPEN_SOURCE && _XOPEN_SOURCE_EXTENDED)

Glibc 2.23 and earlier:

_XOPEN_SOURCE

ptsname_r():

_GNU_SOURCE

DESCRIPTION

The ptsname() function returns the name of the slave pseudoterminal de?

vice corresponding to the master referred to by the file descriptor fd.

The ptsname_r() function is the reentrant equivalent of ptsname(). It returns the name of the slave pseudoterminal device as a null-termi? nated string in the buffer pointed to by buf. The buflen argument specifies the number of bytes available in buf.

RETURN VALUE

On success, ptsname() returns a pointer to a string in static storage which will be overwritten by subsequent calls. This pointer must not

be freed. On failure, NULL is returned.

On success, ptsname_r() returns 0. On failure, an error number is re?

turned to indicate the error.

ERRORS

EINVAL (ptsname_r() only) buf is NULL. (This error is returned only

for glibc 2.25 and earlier.)

ENOTTY fd does not refer to a pseudoterminal master device.

ERANGE (ptsname_r() only) buf is too small.

VERSIONS

ptsname() is provided in glibc since version 2.1.

ATTRIBUTES

For an explanation of the terms used in this section, see at? tributes(7).

?Interface ? Attribute ? Value

?

?

?ptsname() ? Thread safety ? MT-Unsafe race:ptsname ?

?ptsname_r() ? Thread safety ? MT-Safe

CONFORMING TO

ptsname():

POSIX.1-2001, POSIX.1-2008.

ptsname() is part of the UNIX 98 pseudoterminal support (see pts(4)).

ptsname_r() is a Linux extension, that is proposed for inclusion in the

next major revision of POSIX.1 (Issue 8). A version of this function is documented on Tru64 and HP-UX, but on those implementations, -1 is returned on error, with errno set to indicate the error. Avoid using this function in portable programs.

SEE ALSO

grantpt(3), posix_openpt(3), ttyname(3), unlockpt(3), pts(4), pty(7)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

2020-06-09 PTSNAME(3)